
Icepack Documentation

Release 1.0.0

CICE Consortium

Feb 11, 2018

CONTENTS

1	Introduction - Icepack	1
1.1	About Icepack	1
1.2	Quick Start	1
1.3	Major Icepack updates	2
1.4	Acknowledgements	2
1.5	Copyright	2
2	Science Guide	5
2.1	Atmosphere and ocean boundary forcing	5
2.2	Ice thickness distribution	10
2.3	Tracers	11
2.4	Transport in thickness space	13
2.5	Mechanical redistribution	16
2.6	Thermodynamics	19
2.7	Biogeochemistry	41
3	User Guide	57
3.1	Implementation	57
3.2	Running Icepack	60
3.3	Testing Icepack	66
3.4	Case Settings	74
3.5	Troubleshooting	86
4	Developer Guide	89
4.1	About Development	89
4.2	Icepack Column Physics	89
4.3	Driver Implementation	94
4.4	Scripts Implementation	95
4.5	Adding tracers	96
4.6	Documentation System	98
5	Index of primary variables and parameters	103
6	References	115
	Bibliography	117

INTRODUCTION - ICEPACK

1.1 About Icepack

The column physics package of the sea ice model CICE, “Icepack”, is maintained by the CICE Consortium. This code includes several options for simulating sea ice thermodynamics, mechanical redistribution (ridging) and associated area and thickness changes. In addition, the model supports a number of tracers, including thickness, enthalpy, ice age, first-year ice area, deformed ice area and volume, melt ponds, and biogeochemistry.

Icepack is implemented in CICE as a git submodule. The purpose of Icepack is to provide the column physics model as a separate library for use in other host models such as CICE. Development and testing of CICE and Icepack may be done together, but the repositories are independent.

Icepack consists of three independent parts, the column physics code, the icepack driver that supports stand-alone testing of the column physics code, and the icepack scripts that build and test the Icepack model. The column physics is called from a host (driver) model on a gridpoint by gridpoint basis. Each gridpoint is independent and the host model stores and passes the model state and forcing to the column physics.

This document uses the following text conventions: Variable names used in the code are *typewritten*. Subroutine names are given in *italic*. File and directory names are in **boldface**. Code and scripts are contained in a literal box or *typewritten*. A comprehensive *Index of primary variables and parameters*, including glossary of symbols with many of their values, appears at the end of this guide.

1.2 Quick Start

Download the model from the CICE-Consortium repository, <https://github.com/CICE-Consortium/Icepack>

Instructions for working in github with Icepack (and CICE) can be found in the [CICE Git and Workflow Guide](#).

From your main Icepack directory, execute:

```
./icepack.setup -c ~/mycase1 -m testmachine
cd ~/mycase1
./icepack.build
./icepack.submit
```

`testmachine` is a generic machine name included with the icepack scripts. The local machine name will have to be substituted for `testmachine` and there are working ports for several different machines. However, it may be necessary to port the model to a new machine. See [Porting](#) for more information about how to port and [Scripts](#) for more information about how to use the `icepack.setup` script.

1.3 Major Icepack updates

This model release is Icepack version 1.0.

Modern sea ice models have evolved into highly complex collections of physical parameterizations and infrastructural elements to support various configurations and computational approaches. In particular, numerical models may now be implemented for unstructured grids, requiring new approaches for referencing information in neighboring grid cells and communication information across grid elements. However, a large portion of the physics in sea ice models can be described in a vertical column, without reference to neighboring grid cells. This part of the CICE model has been separated into its own modular software package, Icepack. The column physics code was separated from CICE version 5.1.2 by removing all references to the horizontal grid and other infrastructural CICE elements (e.g. MPI tasks, calendar).

To allow the column physics to be developed and maintained as a software package independent of CICE, a simplified driver was created along with a full test suite and scripts for building and running the code. Icepack includes the simplified driver and scripts for configuring various tests of the column physics code in `columnphysics/`.

Enhancements and bug fixes made to Icepack since the last numbered release can be found on the Icepack wiki <https://github.com/CICE-Consortium/Icepack/wiki/Recent-changes>. Major changes with each Icepack release (found here: <https://github.com/CICE-Consortium/Icepack/releases>) will be included as release notes.

1.4 Acknowledgements

This work has been completed through the CICE Consortium and its members with funding through the Department of Energy, Department of Defense (Navy), Department of Commerce (NOAA), National Science Foundation and Environment and Climate Change Canada. Special thanks are due to the following people:

- Elizabeth Hunke, Nicole Jeffery, Adrian Turner and Chris Newman at Los Alamos National Laboratory
- David Bailey, Alice DuVivier and Marika Holland at the National Center for Atmospheric Research
- Rick Allard, Matt Turner and David Hebert at the Naval Research Laboratory, Stennis Space Center,
- Andrew Roberts of the Naval Postgraduate School,
- Jean-Francois Lemieux and Frederic Dupont of Environment and Climate Change Canada,
- Tony Craig and his supporters at the National Center for Atmospheric Research, the Naval Postgraduate School, and NOAA National Weather Service,
- Cecilia Bitz at the University of Washington, for her column forcing data,
- and many others who contributed to previous versions of CICE.

1.5 Copyright

© Copyright 2018, Los Alamos National Security LLC. All rights reserved. This software was produced under U.S. Government contract DE-AC52-06NA25396 for Los Alamos National Laboratory (LANL), which is operated by Los Alamos National Security, LLC for the U.S. Department of Energy. The U.S. Government has rights to use, reproduce, and distribute this software. NEITHER THE GOVERNMENT NOR LOS ALAMOS NATIONAL SECURITY, LLC MAKES ANY WARRANTY, EXPRESS OR IMPLIED, OR ASSUMES ANY LIABILITY FOR THE USE OF THIS SOFTWARE. If software is modified to produce derivative works, such modified software should be clearly marked, so as not to confuse it with the version available from LANL.

Additionally, redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Los Alamos National Security, LLC, Los Alamos National Laboratory, LANL, the U.S. Government, nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY LOS ALAMOS NATIONAL SECURITY, LLC AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL LOS ALAMOS NATIONAL SECURITY, LLC OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

2.1 Atmosphere and ocean boundary forcing

Table 2.1: *External forcing data that are relevant to Icepack*

Variable	Description	External Interactions
z_o	Atmosphere level height	From <i>atmosphere model</i> to <i>sea ice model</i>
\vec{U}_a	Wind velocity	From <i>atmosphere model</i> to <i>sea ice model</i>
Q_a	Specific humidity	From <i>atmosphere model</i> to <i>sea ice model</i>
ρ_a	Air density	From <i>atmosphere model</i> to <i>sea ice model</i>
Θ_a	Air potential temperature	From <i>atmosphere model</i> to <i>sea ice model</i>
T_a	Air temperature	From <i>atmosphere model</i> to <i>sea ice model</i>
$F_{sw\downarrow}$	Incoming shortwave radiation (4 bands)	From <i>atmosphere model</i> to <i>sea ice model</i>
$F_{L\downarrow}$	Incoming longwave radiation	From <i>atmosphere model</i> to <i>sea ice model</i>
F_{rain}	Rainfall rate	From <i>atmosphere model</i> to <i>sea ice model</i>
F_{snow}	Snowfall rate	From <i>atmosphere model</i> to <i>sea ice model</i>
F_{frzmlt}	Freezing/melting potential	From <i>ocean model</i> to <i>sea ice model</i>
T_w	Sea surface temperature	From <i>ocean model</i> to <i>sea ice model</i>
S	Sea surface salinity	From <i>ocean model</i> to <i>sea ice model</i>
\vec{U}_w	Surface ocean currents	From <i>ocean model</i> to <i>sea ice model</i> (available in Icepack driver, not used directly in column physics)
$\vec{\tau}_a$	Wind stress	From <i>sea ice model</i> to <i>atmosphere model</i>
F_s	Sensible heat flux	From <i>sea ice model</i> to <i>atmosphere model</i>
F_l	Latent heat flux	From <i>sea ice model</i> to <i>atmosphere model</i>
$F_{L\uparrow}$	Outgoing longwave radiation	From <i>sea ice model</i> to <i>atmosphere model</i>
F_{evap}	Evaporated water	From <i>sea ice model</i> to <i>atmosphere model</i>
α	Surface albedo (4 bands)	From <i>sea ice model</i> to <i>atmosphere model</i>
T_{sfc}	Surface temperature	From <i>sea ice model</i> to <i>atmosphere model</i>
$F_{sw\downarrow}$	Penetrating shortwave radiation	From <i>sea ice model</i> to <i>ocean model</i>
F_{water}	Fresh water flux	From <i>sea ice model</i> to <i>ocean model</i>
F_{hocn}	Net heat flux to ocean	From <i>sea ice model</i> to <i>ocean model</i>
F_{salt}	Salt flux	From <i>sea ice model</i> to <i>ocean model</i>
$\vec{\tau}_w$	Ice-ocean stress	From <i>sea ice model</i> to <i>ocean model</i>
F_{bio}	Biogeochemical fluxes	From <i>sea ice model</i> to <i>ocean model</i>
a_i	Ice fraction	From <i>sea ice model</i> to both <i>ocean</i> and <i>atmosphere models</i>
T_a^{ref}	2m reference temperature (diagnostic)	From <i>sea ice model</i> to both <i>ocean</i> and <i>atmosphere models</i>

Continued on next page

Table 2.1 – continued from previous page

Variable	Description	External Interactions
Q_a^{ref}	2m reference humidity (diagnostic)	From <i>sea ice model</i> to both <i>ocean and atmosphere models</i>
F_{swabs}	Absorbed shortwave (diagnostic)	From <i>sea ice model</i> to both <i>ocean and atmosphere models</i>

The ice fraction a_i (aice) is the total fractional ice coverage of a grid cell. That is, in each cell,

$$\begin{aligned} a_i &= 0 && \text{if there is no ice} \\ a_i &= 1 && \text{if there is no open water} \\ 0 < a_i < 1 && \text{if there is both ice and open water,} \end{aligned}$$

where a_i is the sum of fractional ice areas for each category of ice. The ice fraction is used by the flux coupler to merge fluxes from the sea ice model with fluxes from the other earth system components. For example, the penetrating shortwave radiation flux, weighted by a_i , is combined with the net shortwave radiation flux through ice-free leads, weighted by $(1 - a_i)$, to obtain the net shortwave flux into the ocean over the entire grid cell. The CESM flux coupler requires the fluxes to be divided by the total ice area so that the ice and land models are treated identically (land also may occupy less than 100% of an atmospheric grid cell). These fluxes are “per unit ice area” rather than “per unit grid cell area.”

In some coupled climate models (for example, recent versions of the U.K. Hadley Centre model) the surface air temperature and fluxes are computed within the atmosphere model and are passed to CICE for use in the column physics. In this case the logical parameter `calc_Tsfc` in *ice_therm_vertical* is set to false. The fields `fsurfn` (the net surface heat flux from the atmosphere), `flatn` (the surface latent heat flux), and `fcondtopn` (the conductive flux at the top surface) for each ice thickness category are copied or derived from the input coupler fluxes and are passed to the thermodynamic driver subroutine, *thermo_vertical*. At the end of the time step, the surface temperature and effective conductivity (i.e., thermal conductivity divided by thickness) of the top ice/snow layer in each category are returned to the atmosphere model via the coupler. Since the ice surface temperature is treated explicitly, the effective conductivity may need to be limited to ensure stability. As a result, accuracy may be significantly reduced, especially for thin ice or snow layers. A more stable and accurate procedure would be to compute the temperature profiles for both the atmosphere and ice, together with the surface fluxes, in a single implicit calculation. This was judged impractical, however, given that the atmosphere and sea ice models generally exist on different grids and/or processor sets.

2.1.1 Atmosphere

The wind velocity, specific humidity, air density and potential temperature at the given level height z_o are used to compute transfer coefficients used in formulas for the surface wind stress and turbulent heat fluxes $\vec{\tau}_a$, F_s , and F_l , as described below. The sensible and latent heat fluxes, F_s and F_l , along with shortwave and longwave radiation, $F_{sw\downarrow}$, $F_{L\downarrow}$ and $F_{L\uparrow}$, are included in the flux balance that determines the ice or snow surface temperature when `calc_Tsfc` is true. As described in the *Thermodynamics* section, these fluxes depend nonlinearly on the ice surface temperature T_{sfc} . The balance equation is iterated until convergence, and the resulting fluxes and T_{sfc} are then passed to the flux coupler.

The snowfall precipitation rate (provided as liquid water equivalent and converted by the ice model to snow depth) also contributes to the heat and water mass budgets of the ice layer. Melt ponds generally form on the ice surface in the Arctic and refreeze later in the fall, reducing the total amount of fresh water that reaches the ocean and altering the heat budget of the ice; this version includes two new melt pond parameterizations. Rain and all melted snow end up in the ocean.

Wind stress and transfer coefficients for the turbulent heat fluxes are computed in subroutine *atmo_boundary_layer* following [28], with additions and changes as detailed in Appendix A of [42] for high frequency coupling (namelist variable `highfreq`). The resulting equations are provided here.

The wind stress and turbulent heat flux calculation accounts for both stable and unstable atmosphere–ice boundary layers. Define the “stability”

$$\Upsilon = \frac{\kappa g z_o}{u^{*2}} \left(\frac{\Theta^*}{\Theta_a (1 + 0.606 Q_a)} + \frac{Q^*}{1/0.606 + Q_a} \right), \quad (2.1)$$

where κ is the von Karman constant, g is gravitational acceleration, and u^* , Θ^* and Q^* are turbulent scales for velocity difference, temperature, and humidity, respectively, given the ice velocity \vec{U}_i :

$$\begin{aligned} u^* &= c_u \max \left(U_{\Delta \min}, \left| \vec{U}_a - \vec{U}_i \right| \right), \\ \Theta^* &= c_\theta (\Theta_a - T_{sfc}), \\ Q^* &= c_q (Q_a - Q_{sfc}). \end{aligned} \quad (2.2)$$

Within the u^* expression, $U_{\Delta \min}$ is the minimum allowable value of $|\vec{U}_a - \vec{U}_i|$, which is set to of 0.5 m/s for high frequency coupling (`highfreq=.true.`). When high frequency coupling is turned off (`highfreq=.false.`), it is assumed in equation (2.2) that:

$$\vec{U}_a - \vec{U}_i \approx \vec{U}_a \quad (2.3)$$

and a higher threshold is taken for $U_{\Delta \min}$ of 1m/s. Equation (2.3) is a poor assumption when resolving inertial oscillations in ice-ocean configurations where the ice velocity vector may make a complete rotation over a period of ≥ 11.96 hours, as discussed in [42]. However, (2.3) is acceptable for low frequency ice-ocean coupling on the order of a day or more, when transient ice-ocean Ekman transport is effectively filtered from the model solution. For the Θ^* and Q^* terms in (2.2), T_{sfc} and Q_{sfc} are the surface temperature and specific humidity, respectively. The latter is calculated by assuming a saturated surface, as described in the *Thermodynamic surface forcing balance* section.

Neglecting form drag, the exchange coefficients c_u , c_θ and c_q are initialized as

$$\frac{\kappa}{\ln(z_{ref}/z_{ice})} \quad (2.4)$$

and updated during a short iteration, as they depend upon the turbulent scales. The number of iterations is set by the namelist variable `natmiter`, nominally set to five but sometimes increased by users employing the `highfreq` option. Here, z_{ref} is a reference height of 10m and z_{ice} is the roughness length scale for the given sea ice category. Υ is constrained to have magnitude less than 10. Further, defining $\chi = (1 - 16\Upsilon)^{0.25}$ and $\chi \geq 1$, the “integrated flux profiles” for momentum and stability in the unstable ($\Upsilon < 0$) case are given by

$$\begin{aligned} \psi_m &= 2 \ln [0.5(1 + \chi)] + \ln [0.5(1 + \chi^2)] - 2 \tan^{-1} \chi + \frac{\pi}{2}, \\ \psi_s &= 2 \ln [0.5(1 + \chi^2)]. \end{aligned} \quad (2.5)$$

In a departure from the parameterization used in [28], we use profiles for the stable case following [27],

$$\psi_m = \psi_s = -[0.7\Upsilon + 0.75(\Upsilon - 14.3) \exp(-0.35\Upsilon) + 10.7]. \quad (2.6)$$

The coefficients are then updated as

$$\begin{aligned} c'_u &= \frac{c_u}{1 + c_u(\lambda - \psi_m)/\kappa} \\ c'_\theta &= \frac{c_\theta}{1 + c_\theta(\lambda - \psi_s)/\kappa} \\ c'_q &= c'_\theta \end{aligned} \quad (2.7)$$

where $\lambda = \ln(z_o/z_{ref})$. The first iteration ends with new turbulent scales from equations (2.2). After `natmiter` iterations the latent and sensible heat flux coefficients are computed, along with the wind stress:

$$\begin{aligned} C_l &= \rho_a (L_{vap} + L_{ice}) u^* c_q \\ C_s &= \rho_a c_p u^* c'_\theta + 1 \\ \vec{\tau}_a &= \frac{\rho_a (u^*)^2 (\vec{U}_a - \vec{U}_i)}{|\vec{U}_a - \vec{U}_i|} \end{aligned} \quad (2.8)$$

where L_{vap} and L_{ice} are latent heats of vaporization and fusion, ρ_a is the density of air and c_p is its specific heat. Again following [27], we have added a constant to the sensible heat flux coefficient in order to allow some heat to pass between the atmosphere and the ice surface in stable, calm conditions. For the atmospheric stress term in (2.8), we make the assumption in (2.3) when `highfreq=false`.

The atmospheric reference temperature T_a^{ref} is computed from T_a and T_{sfc} using the coefficients c_u , c_θ and c_q . Although the sea ice model does not use this quantity, it is convenient for the ice model to perform this calculation. The atmospheric reference temperature is returned to the flux coupler as a climate diagnostic. The same is true for the reference humidity, Q_a^{ref} .

Additional details about the latent and sensible heat fluxes and other quantities referred to here can be found in the [Thermodynamic surface forcing balance](#) section.

2.1.2 Ocean

New sea ice forms when the ocean temperature drops below its freezing temperature. In the Bitz and Lipscomb thermodynamics, [6] $T_f = -\mu S$, where S is the seawater salinity and $\mu = 0.054^\circ/\text{ppt}$ is the ratio of the freezing temperature of brine to its salinity (linear liquidus approximation). For the mushy thermodynamics, T_f is given by a piecewise linear liquidus relation. The ocean model calculates the new ice formation; if the freezing/melting potential F_{fzmelt} is positive, its value represents a certain amount of frazil ice that has formed in one or more layers of the ocean and floated to the surface. (The ocean model assumes that the amount of new ice implied by the freezing potential actually forms.)

If F_{fzmelt} is negative, it is used to heat already existing ice from below. In particular, the sea surface temperature and salinity are used to compute an oceanic heat flux F_w ($|F_w| \leq |F_{fzmelt}|$) which is applied at the bottom of the ice. The portion of the melting potential actually used to melt ice is returned to the coupler in F_{hocr} . The ocean model adjusts its own heat budget with this quantity, assuming that the rest of the flux remained in the ocean.

In addition to runoff from rain and melted snow, the fresh water flux F_{water} includes ice melt water from the top surface and water frozen (a negative flux) or melted at the bottom surface of the ice. This flux is computed as the net change of fresh water in the ice and snow volume over the coupling time step, excluding frazil ice formation and newly accumulated snow. Setting the namelist option `update_ocn_f` to true causes frazil ice to be included in the fresh water and salt fluxes.

There is a flux of salt into the ocean under melting conditions, and a (negative) flux when sea water is freezing. However, melting sea ice ultimately freshens the top ocean layer, since the ocean is much more saline than the ice. The ice model passes the net flux of salt F_{salt} to the flux coupler, based on the net change in salt for ice in all categories. In the present configuration, `ice_ref_salinity` is used for computing the salt flux, although the ice salinity used in the thermodynamic calculation has differing values in the ice layers.

A fraction of the incoming shortwave $F_{sw\downarrow}$ penetrates the snow and ice layers and passes into the ocean, as described in the [Thermodynamic surface forcing balance](#) section.

A thermodynamic slab ocean mixed-layer parameterization is available in `icepack_ocean.F90` and can be run in the full CICE configuration. The turbulent fluxes are computed above the water surface using the same parameterizations as for sea ice, but with parameters appropriate for the ocean. The surface flux balance takes into account the turbulent fluxes, oceanic heat fluxes from below the mixed layer, and shortwave and longwave radiation, including that passing through the sea ice into the ocean. If the resulting sea surface temperature falls below the salinity-dependent freezing point, then new ice (frazil) forms. Otherwise, heat is made available for melting the ice.

2.1.3 Variable exchange coefficients

In the default configuration, atmospheric and oceanic neutral drag coefficients (c_u and c_w) are assumed constant in time and space. These constants are chosen to reflect friction associated with an effective sea ice surface roughness at the ice-atmosphere and ice-ocean interfaces. Sea ice (in both Arctic and Antarctic) contains pressure ridges as well as floe and melt pond edges that act as discrete obstructions to the flow of air or water past the ice, and are a source

of form drag. Following [52] and based on recent theoretical developments [34][33], the neutral drag coefficients can now be estimated from properties of the ice cover such as ice concentration, vertical extent and area of the ridges, freeboard and floe draft, and size of floes and melt ponds. The new parameterization allows the drag coefficients to be coupled to the sea ice state and therefore to evolve spatially and temporally. This parameterization is contained in the subroutine *neutral_drag_coeffs* and is accessed by setting `formdrag = true` in the namelist. (Note: see also *Known bugs and other issues*.)

Following [52], consider the general case of fluid flow obstructed by N randomly oriented obstacles of height H and transverse length L_y , distributed on a domain surface area S_T . Under the assumption of a logarithmic fluid velocity profile, the general formulation of the form drag coefficient can be expressed as

$$C_d = \frac{N c S_c^2 \gamma L_y H}{2 S_T} \left[\frac{\ln(H/z_0)}{\ln(z_{ref}/z_0)} \right]^2, \quad (2.9)$$

where z_0 is a roughness length parameter at the top or bottom surface of the ice, γ is a geometric factor, c is the resistance coefficient of a single obstacle, and S_c is a sheltering function that takes into account the shielding effect of the obstacle,

$$S_c = (1 - \exp(-s_l D/H))^{1/2}, \quad (2.10)$$

with D the distance between two obstacles and s_l an attenuation parameter.

As in the original drag formulation in CICE (*Atmosphere* and *Ocean* sections), c_u and c_w along with the transfer coefficients for sensible heat, c_θ , and latent heat, c_q , are initialized to a situation corresponding to neutral atmosphere–ice and ocean–ice boundary layers. The corresponding neutral exchange coefficients are then replaced by coefficients that explicitly account for form drag, expressed in terms of various contributions as

$$\text{Cdn_atm} = \text{Cdn_atm_rdg} + \text{Cdn_atm_floe} + \text{Cdn_atm_skin} + \text{Cdn_atm_pond}, \quad (2.11)$$

$$\text{Cdn_ocn} = \text{Cdn_ocn_rdg} + \text{Cdn_ocn_floe} + \text{Cdn_ocn_skin}. \quad (2.12)$$

The contributions to form drag from ridges (and keels underneath the ice), floe edges and melt pond edges can be expressed using the general formulation of equation (2.9) (see [52] for details). Individual terms in equation (2.12) are fully described in [52]. Following [3] the skin drag coefficient is parametrized as

$$\text{Cdn_(\text{atm/ocn})_skin} = a_i \left(1 - m_{(s/k)} \frac{H_{(s/k)}}{D_{(s/k)}} \right) c_{s(s/k)}, \text{ if } \frac{H_{(s/k)}}{D_{(s/k)}} \geq \frac{1}{m_{(s/k)}}, \quad (2.13)$$

where m_s (m_k) is a sheltering parameter that depends on the average sail (keel) height, H_s (H_k), but is often assumed constant, D_s (D_k) is the average distance between sails (keels), and c_{ss} (c_{sk}) is the unobstructed atmospheric (oceanic) skin drag that would be attained in the absence of sails (keels) and with complete ice coverage, $a_{ice} = 1$.

Calculation of equations (2.9) – (2.13) requires that small-scale geometrical properties of the ice cover be related to average grid cell quantities already computed in the sea ice model. These intermediate quantities are briefly presented here and described in more detail in [52]. The sail height is given by

$$H_s = 2 \frac{v_{rdg}}{a_{rdg}} \left(\frac{\alpha \tan \alpha_k R_d + \beta \tan \alpha_s R_h}{\phi_r \tan \alpha_k R_d + \phi_k \tan \alpha_s R_h^2} \right), \quad (2.14)$$

and the distance between sails

$$D_s = 2 H_s \frac{a_i}{a_{rdg}} \left(\frac{\alpha}{\tan \alpha_s} + \frac{\beta}{\tan \alpha_k} \frac{R_h}{R_d} \right), \quad (2.15)$$

where $0 < \alpha < 1$ and $0 < \beta < 1$ are weight functions, α_s and α_k are the sail and keel slope, ϕ_s and ϕ_k are constant porosities for the sails and keels, and we assume constant ratios for the average keel depth and sail height

($H_k/H_s = R_h$) and for the average distances between keels and between sails ($D_k/D_s = R_d$). With the assumption of hydrostatic equilibrium, the effective ice plus snow freeboard is $H_f = \bar{h}_i(1 - \rho_i/\rho_w) + \bar{h}_s(1 - \rho_s/\rho_w)$, where ρ_i , ρ_w and ρ_s are respectively the densities of sea ice, water and snow, \bar{h}_i is the mean ice thickness and \bar{h}_s is the mean snow thickness (means taken over the ice covered regions). For the melt pond edge elevation we assume that the melt pond surface is at the same level as the ocean surface surrounding the floes [13][14][15] and use the simplification $H_p = H_f$. Finally to estimate the typical floe size L_A , distance between floes, D_F , and melt pond size, L_P we use the parameterizations of [34] to relate these quantities to the ice and pond concentrations. All of these intermediate quantities are available for output, along with `Cdn_atm`, `Cdn_ocn` and the ratio `Cdn_atm_ratio_n` between the total atmospheric drag and the atmospheric neutral drag coefficient.

We assume that the total neutral drag coefficients are thickness category independent, but through their dependence on the diagnostic variables described above, they vary both spatially and temporally. The total drag coefficients and heat transfer coefficients will also depend on the type of stratification of the atmosphere and the ocean, and we use the parameterization described in the *Atmosphere* section that accounts for both stable and unstable atmosphere–ice boundary layers. In contrast to the neutral drag coefficients the stability effect of the atmospheric boundary layer is calculated separately for each ice thickness category.

The transfer coefficient for oceanic heat flux to the bottom of the ice may be varied based on form drag considerations by setting the namelist variable `fbot_xfer_type` to `Cdn_ocn`; this is recommended when using the form drag parameterization. The default value of the transfer coefficient is 0.006 (`fbot_xfer_type = 'constant'`).

2.2 Ice thickness distribution

The Arctic and Antarctic sea ice packs are mixtures of open water, thin first-year ice, thicker multiyear ice, and thick pressure ridges. The thermodynamic and dynamic properties of the ice pack depend on how much ice lies in each thickness range. Thus the basic problem in sea ice modeling is to describe the evolution of the ice thickness distribution (ITD) in time and space.

The fundamental equation solved by CICE is [50]:

$$\frac{\partial g}{\partial t} = -\nabla \cdot (g\mathbf{u}) - \frac{\partial}{\partial h}(fg) + \psi - L, \quad (2.16)$$

where \mathbf{u} is the horizontal ice velocity, $\nabla = (\frac{\partial}{\partial x}, \frac{\partial}{\partial y})$, f is the rate of thermodynamic ice growth, ψ is a ridging redistribution function, L is the lateral melt rate and g is the ice thickness distribution function. We define $g(\mathbf{x}, h, t) dh$ as the fractional area covered by ice in the thickness range $(h, h + dh)$ at a given time and location. Icepack represents all of the terms in this equation except for the divergence (the first term on the right).

Equation (2.16) is solved by partitioning the ice pack in each grid cell into discrete thickness categories. The number of categories can be set by the user, with a default value $N_C = 5$. (Five categories, plus open water, are generally sufficient to simulate the annual cycles of ice thickness, ice strength, and surface fluxes [5][31].) Each category n has lower thickness bound H_{n-1} and upper bound H_n . The lower bound of the thinnest ice category, H_0 , is set to zero. The other boundaries are chosen with greater resolution for small h , since the properties of the ice pack are especially sensitive to the amount of thin ice [35]. The continuous function $g(h)$ is replaced by the discrete variable a_{in} , defined as the fractional area covered by ice in the open water by a_{i0} , giving $\sum_{n=0}^{N_C} a_{in} = 1$ by definition.

Category boundaries are computed in `init_itd` using one of several formulas, summarized in Table *Lower boundary values*. Setting the namelist variable `kcatbound` equal to 0 or 1 gives lower thickness boundaries for any number of thickness categories N_C . Table *Lower boundary values* shows the boundary values for $N_C = 5$ and linear remapping of the ice thickness distribution. A third option specifies the boundaries based on the World Meteorological Organization classification; the full WMO thickness distribution is used if $N_C = 7$; if $N_C = 5$ or 6, some of the thinner categories are combined. The original formula (`kcatbound = 0`) is the default. Category boundaries differ from those shown in Table *Lower boundary values* for the delta-function ITD. Users may substitute their own preferred boundaries in `init_itd`.

Table *Lower boundary values* shows lower boundary values for thickness categories, in meters, for the three distribution options (“*kcatbound*”) and linear remapping (“*kitd*” = 1). In the WMO case, the distribution used depends on the number of categories used.

Table 2.2: *Lower boundary values*

distribution	original	round	WMO		
kcatbound	0	1	2		
N_C	5	5	5	6	7
categories	lower bound (m)				
1	0.00	0.00	0.00	0.00	0.00
2	0.64	0.60	0.30	0.15	0.10
3	1.39	1.40	0.70	0.30	0.15
4	2.47	2.40	1.20	0.70	0.30
5	4.57	3.60	2.00	1.20	0.70
6				2.00	1.20
7					2.00

2.3 Tracers

Numerous tracers are available with the column physics. Several of these are required (surface temperature and thickness, salinity and enthalpy of ice and snow layers), and many others are options. For instance, there are tracers to track the age of the ice; the area of first-year ice, fractions of ice area and volume that are level, from which the amount of deformed ice can be calculated; pond area, pond volume and volume of ice covering ponds; aerosols and numerous other biogeochemical tracers. Most of these tracers are presented in later sections. Here we describe the ice age tracers and how tracers may depend on other tracers, using the pond tracers as an example.

2.3.1 Ice age

The age of the ice, τ_{age} , is treated as an ice-volume tracer ($trcr_depend = 1$). It is initialized at 0 when ice forms as frazil, and the ice ages the length of the timestep during each timestep. Freezing directly onto the bottom of the ice does not affect the age, nor does melting. Mechanical redistribution processes and advection alter the age of ice in any given grid cell in a conservative manner following changes in ice area. The sea ice age tracer is validated in [22].

Another age-related tracer, the area covered by first-year ice a_{FY} , is an area tracer ($trcr_depend = 0$) that corresponds more closely to satellite-derived ice age data for first-year ice than does τ_{age} . It is re-initialized each year on 15 September ($yday = 259$) in the northern hemisphere and 15 March ($yday = 75$) in the southern hemisphere, in non-leap years. This tracer is increased when new ice forms in open water, in subroutine `add_new_ice` in `icepack_therm_itd.F90`. The first-year area tracer is discussed in [2].

2.3.2 Tracers that depend on other tracers

Tracers may be defined that depend on other tracers. Melt pond tracers provide an example (these equations pertain to cesm and topo tracers; level-ice tracers are similar with an extra factor of a_{lvl} , see Equations (2.68)–(2.71)). Conservation equations for pond area fraction $a_{pnd}a_i$ and pond volume $h_{pnd}a_{pnd}a_i$, given the ice velocity \mathbf{u} , are

$$\frac{\partial}{\partial t}(a_{pnd}a_i) + \nabla \cdot (a_{pnd}a_i\mathbf{u}) = 0, \quad (2.17)$$

$$\frac{\partial}{\partial t}(h_{pnd}a_{pnd}a_i) + \nabla \cdot (h_{pnd}a_{pnd}a_i\mathbf{u}) = 0. \quad (2.18)$$

These equations represent quantities within one thickness category; all melt pond calculations are performed for each category, separately. Equation (2.18) expresses conservation of melt pond volume, but in this form highlights that the quantity tracked in the code is the pond depth tracer h_{pnd} , which depends on the pond area tracer a_{pnd} . Likewise, a_{pnd} is a tracer on ice area (Equation (2.17)), which is a state variable, not a tracer.

For a generic quantity q that represents a mean value over the ice fraction, qa_i is the average value over the grid cell. Thus for cesm or topo melt ponds, h_{pnd} can be considered the actual pond depth, $h_{pnd}a_{pnd}$ is the mean pond depth over the sea ice, and $h_{pnd}a_{pnd}a_i$ is the mean pond depth over the grid cell. These quantities are illustrated in Figure [Melt pond tracer definitions](#). The graphic on the right illustrates the *grid cell* fraction of ponds or level ice as defined by the tracers. The chart on the left provides corresponding ice thickness and pond depth averages over the grid cell, sea ice and pond area fractions.




Fig. 2.1: Melt pond tracer definitions

Tracers may need to be modified for physical reasons outside of the “core” module or subroutine describing their evolution. For example, when new ice forms in open water, the new ice does not yet have ponds on it. Likewise when sea ice deforms, we assume that pond water (and ice) on the portion of ice that ridges is lost to the ocean.

When new ice is added to a grid cell, the *grid cell* total area of melt ponds is preserved within each category gaining ice, $a_{pnd}^{t+\Delta t} a_i^{t+\Delta t} = a_{pnd}^t a_i^t$, or

$$a_{pnd}^{t+\Delta t} = \frac{a_{pnd}^t a_i^t}{a_i^{t+\Delta t}}. \quad (2.19)$$

Similar calculations are performed for all tracer types, for example tracer-on-tracer dependencies such as h_{pnd} , when needed:

$$h_{pnd}^{t+\Delta t} = \frac{h_{pnd}^t a_{pnd}^t a_i^t}{a_{pnd}^{t+\Delta t} a_i^{t+\Delta t}}. \quad (2.20)$$

In this case (adding new ice), h_{pnd} does not change because $a_{pnd}^{t+\Delta t} a_i^{t+\Delta t} = a_{pnd}^t a_i^t$.

When ice is transferred between two thickness categories, we conserve the total pond area summed over categories n ,

$$\sum_n a_{pnd}^{t+\Delta t}(n) a_i^{t+\Delta t}(n) = \sum_n a_{pnd}^t(n) a_i^t(n). \quad (2.21)$$

Thus,

$$\begin{aligned} a_{pnd}^{t+\Delta t}(m) &= \frac{\sum_n a_{pnd}^t(n) a_i^t(n) - \sum_{n \neq m} a_{pnd}^{t+\Delta t}(n) a_i^{t+\Delta t}(n)}{a_i^{t+\Delta t}(m)} \\ &= \frac{a_{pnd}^t(m) a_i^t(m) + \sum_{n \neq m} \Delta(a_{pnd} a_i)^{t+\Delta t}}{a_i^{t+\Delta t}(m)} \end{aligned} \quad (2.22)$$

This is more complicated because of the Δ term on the right-hand side, which is handled in subroutine *icepack_compute_tracers*. Such tracer calculations are scattered throughout the code, wherever there are changes to the ice thickness distribution.

Note that if a quantity such as a_{pnd} becomes zero in a grid cell's thickness category, then all tracers that depend on it also become zero. If a tracer should be conserved (e.g., aerosols and the liquid water in topo ponds), additional code must be added to track changes in the conserved quantity.

Tracer dependencies and conserved quantities associated with tracers are tracked using the arrays `trcr_depend`, which defines the type of dependency (area, volume, snow, etc), `n_trcr_strata`, the number of underlying layers, `nt_strata`, the indices of the underlying layers, and `trcr_base`, a mask that is one for the tracer dependency and zero otherwise. These arrays are used to convert between the tracer values themselves and the conserved forms.

More information about the melt pond schemes is in the [Melt ponds](#) section.

2.4 Transport in thickness space

Next we solve the equation for ice transport in thickness space due to thermodynamic growth and melt,

$$\frac{\partial g}{\partial t} + \frac{\partial}{\partial h}(fg) = 0, \quad (2.23)$$

which is obtained from Equation (2.16) by neglecting the first and third terms on the right-hand side. We use the remapping method of [31], in which thickness categories are represented as Lagrangian grid cells whose boundaries are projected forward in time. The thickness distribution function g is approximated as a linear function of h in each displaced category and is then remapped onto the original thickness categories. This method is numerically smooth and is not too diffusive. It can be viewed as a 1D simplification of the 2D incremental remapping scheme described above.

We first compute the displacement of category boundaries in thickness space. Assume that at time m the ice areas a_n^m and mean ice thicknesses h_n^m are known for each thickness category. (For now we omit the subscript i that distinguishes ice from snow.) We use a thermodynamic model (*Thermodynamics*) to compute the new mean thicknesses h_n^{m+1} at time $m + 1$. The time step must be small enough that trajectories do not cross; i.e., $h_n^{m+1} < h_{n+1}^{m+1}$ for each pair of adjacent categories. The growth rate at $h = h_n$ is given by $f_n = (h_n^{m+1} - h_n^m)/\Delta t$. By linear interpolation we estimate the growth rate F_n at the upper category boundary H_n :

$$F_n = f_n + \frac{f_{n+1} - f_n}{h_{n+1} - h_n} (H_n - h_n). \quad (2.24)$$

If a_n or $a_{n+1} = 0$, F_n is set to the growth rate in the nonzero category, and if $a_n = a_{n+1} = 0$, we set $F_n = 0$. The temporary displaced boundaries are given by

$$H_n^* = H_n + F_n \Delta t, \quad n = 1 \text{ to } N - 1 \quad (2.25)$$

The boundaries must not be displaced by more than one category to the left or right; that is, we require $H_{n-1} < H_n^* < H_{n+1}$. Without this requirement we would need to do a general remapping rather than an incremental remapping, at the cost of added complexity.

Next we construct $g(h)$ in the displaced thickness categories. The ice areas in the displaced categories are $a_n^{m+1} = a_n^m$, since area is conserved following the motion in thickness space (i.e., during vertical ice growth or melting). The new ice volumes are $v_n^{m+1} = (a_n h_n)^{m+1} = a_n^m h_n^{m+1}$. For conciseness, define $H_L = H_{n-1}^*$ and $H_R = H_n^*$ and drop the time index $m + 1$. We wish to construct a continuous function $g(h)$ within each category such that the total area and volume at time $m + 1$ are a_n and v_n , respectively:

$$\int_{H_L}^{H_R} g \, dh = a_n, \quad (2.26)$$

$$\int_{H_L}^{H_R} h g dh = v_n. \quad (2.27)$$

The simplest polynomial that can satisfy both equations is a line. It is convenient to change coordinates, writing $g(\eta) = g_1\eta + g_0$, where $\eta = h - H_L$ and the coefficients g_0 and g_1 are to be determined. Then Equations (2.26) and (2.27) can be written as

$$g_1 \frac{\eta_R^2}{2} + g_0 \eta_R = a_n, \quad (2.28)$$

$$g_1 \frac{\eta_R^3}{3} + g_0 \frac{\eta_R^2}{2} = a_n \eta_n, \quad (2.29)$$

where $\eta_R = H_R - H_L$ and $\eta_n = h_n - H_L$. These equations have the solution

$$g_0 = \frac{6a_n}{\eta_R^2} \left(\frac{2\eta_R}{3} - \eta_n \right), \quad (2.30)$$

$$g_1 = \frac{12a_n}{\eta_R^3} \left(\eta_n - \frac{\eta_R}{2} \right). \quad (2.31)$$

Since g is linear, its maximum and minimum values lie at the boundaries, $\eta = 0$ and η_R :

$$g(0) = \frac{6a_n}{\eta_R^2} \left(\frac{2\eta_R}{3} - \eta_n \right) = g_0, \quad (2.32)$$

$$g(\eta_R) = \frac{6a_n}{\eta_R^2} \left(\eta_n - \frac{\eta_R}{3} \right). \quad (2.33)$$

Equation (2.32) implies that $g(0) < 0$ when $\eta_n > 2\eta_R/3$, i.e., when h_n lies in the right third of the thickness range (H_L, H_R). Similarly, Equation (2.33) implies that $g(\eta_R) < 0$ when $\eta_n < \eta_R/3$, i.e., when h_n is in the left third of the range. Since negative values of g are unphysical, a different solution is needed when h_n lies outside the central third of the thickness range. If h_n is in the left third of the range, we define a cutoff thickness, $H_C = 3h_n - 2H_L$, and set $g = 0$ between H_C and H_R . Equations (2.30) and (2.28) are then valid with η_R redefined as $H_C - H_L$. And if h_n is in the right third of the range, we define $H_C = 3h_n - 2H_R$ and set $g = 0$ between H_L and H_C . In this case, (2.30) and (2.28) apply with $\eta_R = H_R - H_C$ and $\eta_n = h_n - H_C$.

Figure [Linear approximation of thickness distribution function](#) illustrates the linear reconstruction of g for the simple cases $H_L = 0$, $H_R = 1$, $a_n = 1$, and $h_n = 0.2, 0.4, 0.6$, and 0.8 . Note that g slopes downward ($g_1 < 0$) when h_n is less than the midpoint thickness, $(H_L + H_R)/2 = 1/2$, and upward when h_n exceeds the midpoint thickness. For $h_n = 0.2$ and 0.8 , $g = 0$ over part of the range.

Finally, we remap the thickness distribution to the original boundaries by transferring area and volume between categories. We compute the ice area Δa_n and volume Δv_n between each original boundary H_n and displaced boundary H_n^* . If $H_n^* > H_n$, ice moves from category n to $n + 1$. The area and volume transferred are

$$\Delta a_n = \int_{H_n}^{H_n^*} g dh, \quad (2.34)$$

$$\Delta v_n = \int_{H_n}^{H_n^*} h g dh. \quad (2.35)$$




Fig. 2.2: *Linear approximation of thickness distribution function*

If $H_n^* < H_N$, ice area and volume are transferred from category $n + 1$ to n using Equations (2.34) and (2.35) with the limits of integration reversed. To evaluate the integrals we change coordinates from h to $\eta = h - H_L$, where H_L is the left limit of the range over which $g > 0$, and write $g(\eta)$ using Equations (2.30) and (2.28). In this way we obtain the new areas a_n and volumes v_n between the original boundaries H_{n-1} and H_n in each category. The new thicknesses, $h_n = v_n/a_n$, are guaranteed to lie in the range (H_{n-1}, H_n) . If $g = 0$ in the part of a category that is remapped to a neighboring category, no ice is transferred.

Other conserved quantities are transferred in proportion to the ice volume Δv_{in} . For example, the transferred ice energy in layer k is $\Delta e_{ink} = e_{ink}(\Delta v_{in}/v_{in})$.

The left and right boundaries of the domain require special treatment. If ice is growing in open water at a rate F_0 , the left boundary H_0 is shifted to the right by $F_0 \Delta t$ before g is constructed in category 1, then reset to zero after the remapping is complete. New ice is then added to the grid cell, conserving area, volume, and energy. If ice cannot grow in open water (because the ocean is too warm or the net surface energy flux is downward), H_0 is fixed at zero, and the growth rate at the left boundary is estimated as $F_0 = f_1$. If $F_0 < 0$, all ice thinner than $\Delta h_0 = -F_0 \Delta t$ is assumed to have melted, and the ice area in category 1 is reduced accordingly. The area of new open water is

$$\Delta a_0 = \int_0^{\Delta h_0} g dh. \quad (2.36)$$

The right boundary H_N is not fixed but varies with h_N , the mean ice thickness in the thickest category. Given h_N , we set $H_N = 3h_N - 2H_{N-1}$, which ensures that $g(h) > 0$ for $H_{N-1} < h < H_N$ and $g(h) = 0$ for $h \geq H_N$. No ice crosses the right boundary. If the ice growth or melt rates in a given grid cell are too large, the thickness remapping scheme will not work. Instead, the thickness categories in that grid cell are treated as delta functions following [5], and categories outside their prescribed boundaries are merged with neighboring categories as needed. For time steps of less than a day and category thickness ranges of 10 cm or more, this simplification is needed rarely, if ever.

The linear remapping algorithm for thickness is not monotonic for tracers, although significant errors rarely occur. Usually they appear as snow temperatures (enthalpy) outside the physical range of values in very small snow volumes. In this case we transfer the snow and its heat and tracer contents to the ocean.

2.5 Mechanical redistribution

The last term on the right-hand side of Equation (2.16) is ψ , which describes the redistribution of ice in thickness space due to ridging and other mechanical processes. The mechanical redistribution scheme in Icepack is based on [50], [43], [20], [12], and [32]. This scheme converts thinner ice to thicker ice and is applied after horizontal transport. When the ice is converging, enough ice ridges to ensure that the ice area does not exceed the grid cell area.

First we specify the participation function: the thickness distribution $a_P(h) = b(h)g(h)$ of the ice participating in ridging. (We use “ridging” as shorthand for all forms of mechanical redistribution, including rafting.) The weighting function $b(h)$ favors ridging of thin ice and closing of open water in preference to ridging of thicker ice. There are two options for the form of $b(h)$. If `krdg_partic` = 0 in the namelist, we follow [50] and set

$$b(h) = \begin{cases} \frac{2}{G^*} \left(1 - \frac{G(h)}{G^*}\right) & \text{if } G(h) < G^* \\ 0 & \text{otherwise} \end{cases} \quad (2.37)$$

where $G(h)$ is the fractional area covered by ice thinner than h , and G^* is an empirical constant. Integrating $a_P(h)$ between category boundaries H_{n-1} and H_n , we obtain the mean value of a_P in category n :

$$a_{Pn} = \frac{2}{G^*} (G_n - G_{n-1}) \left(1 - \frac{G_{n-1} + G_n}{2G^*}\right), \quad (2.38)$$

where a_{Pn} is the ratio of the ice area ridging (or open water area closing) in category n to the total area ridging and closing, and G_n is the total fractional ice area in categories 0 to n . Equation (2.38) applies to categories with $G_n < G^*$. If $G_{n-1} < G^* < G_n$, then Equation (2.38) is valid with G^* replacing G_n , and if $G_{n-1} > G^*$, then $a_{Pn} = 0$. If the

open water fraction $a_0 > G^*$, no ice can ridge, because “ridging” simply reduces the area of open water. As in [50] we set $G^* = 0.15$.

If the spatial resolution is too fine for a given time step Δt , the weighting function Equation (2.37) can promote numerical instability. For $\Delta t = 1$ hour, resolutions finer than $\Delta x \sim 10$ km are typically unstable. The instability results from feedback between the ridging scheme and the dynamics via the ice strength. If the strength changes significantly on time scales less than Δt , the viscous-plastic solution of the momentum equation is inaccurate and sometimes oscillatory. As a result, the fields of ice area, thickness, velocity, strength, divergence, and shear can become noisy and unphysical.

A more stable weighting function was suggested by [32]:

$$b(h) = \frac{\exp[-G(h)/a^*]}{a^*[1 - \exp(-1/a^*)]} \quad (2.39)$$

When integrated between category boundaries, Equation (2.39) implies

$$a_{Pn} = \frac{\exp(-G_{n-1}/a^*) - \exp(-G_n/a^*)}{1 - \exp(-1/a^*)} \quad (2.40)$$

This weighting function is used if `krdg_partic = 1` in the namelist. From Equation (2.39), the mean value of G for ice participating in ridging is a^* , as compared to $G^*/3$ for Equation (2.37). For typical ice thickness distributions, setting $a^* = 0.05$ with `krdg_partic = 1` gives participation fractions similar to those given by $G^* = 0.15$ with `krdg_partic = 0`. See [32] for a detailed comparison of these two participation functions.

Thin ice is converted to thick, ridged ice in a way that reduces the total ice area while conserving ice volume and internal energy. There are two namelist options for redistributing ice among thickness categories. If `krdg_redist = 0`, ridging ice of thickness h_n forms ridges whose area is distributed uniformly between $H_{\min} = 2h_n$ and $H_{\max} = 2\sqrt{H^*h_n}$, as in [20]. The default value of H^* is 25 m, as in earlier versions of CICE. Observations suggest that $H^* = 50$ m gives a better fit to first-year ridges [1], although the lower value may be appropriate for multiyear ridges [12]. The ratio of the mean ridge thickness to the thickness of ridging ice is $k_n = (H_{\min} + H_{\max})/(2h_n)$. If the area of category n is reduced by ridging at the rate r_n , the area of thicker categories grows simultaneously at the rate r_n/k_n . Thus the *net* rate of area loss due to ridging of ice in category n is $r_n(1 - 1/k_n)$.

The ridged ice area and volume are apportioned among categories in the thickness range (H_{\min}, H_{\max}) . The fraction of the new ridge area in category m is

$$f_m^{\text{area}} = \frac{H_R - H_L}{H_{\max} - H_{\min}}, \quad (2.41)$$

where $H_L = \max(H_{m-1}, H_{\min})$ and $H_R = \min(H_m, H_{\max})$. The fraction of the ridge volume going to category m is

$$f_m^{\text{vol}} = \frac{(H_R)^2 - (H_L)^2}{(H_{\max})^2 - (H_{\min})^2}. \quad (2.42)$$

This uniform redistribution function tends to produce too little ice in the 3–5 m range and too much ice thicker than 10 m [1]. Observations show that the ITD of ridges is better approximated by a negative exponential. Setting `krdg_redist = 1` gives ridges with an exponential ITD [32]:

$$g_R(h) \propto \exp[-(h - H_{\min})/\lambda] \quad (2.43)$$

for $h \geq H_{\min}$, with $g_R(h) = 0$ for $h < H_{\min}$. Here, λ is an empirical e -folding scale and $H_{\min} = 2h_n$ (where h_n is the thickness of ridging ice). We assume that $\lambda = \mu h_n^{1/2}$, where μ (`mu_rdg`) is a tunable parameter with units . Thus the mean ridge thickness increases in proportion to $h_n^{1/2}$, as in [20]. The value $\mu = 4.0$ gives λ in the range 1–4 m for most ridged ice. Ice strengths with $\mu = 4.0$ and `krdg_redist = 1` are roughly comparable to the strengths with $H^* = 50$ m and `krdg_redist = 0`.

From Equation (2.43) it can be shown that the fractional area going to category m as a result of ridging is

$$f_m^{\text{area}} = \exp[-(H_{m-1} - H_{\min})/\lambda] - \exp[-(H_m - H_{\min})/\lambda]. \quad (2.44)$$

The fractional volume going to category m is

$$f_m^{\text{vol}} = \frac{(H_{m-1} + \lambda) \exp[-(H_{m-1} - H_{\min})/\lambda] - (H_m + \lambda) \exp[-(H_m - H_{\min})/\lambda]}{H_{\min} + \lambda}. \quad (2.45)$$

Equations (2.44) and (2.45) replace Equations (2.41) and (2.42) when `krdg_redist = 1`.

Internal ice energy is transferred between categories in proportion to ice volume. Snow volume and internal energy are transferred in the same way, except that a fraction of the snow may be deposited in the ocean instead of added to the new ridge.

The net area removed by ridging and closing is a function of the strain rates. Let R_{net} be the net rate of area loss for the ice pack (i.e., the rate of open water area closing, plus the net rate of ice area loss due to ridging). Following [12], R_{net} is given by

$$R_{\text{net}} = \frac{C_s}{2} (\Delta - |D_D|) - \min(D_D, 0), \quad (2.46)$$

where C_s is the fraction of shear dissipation energy that contributes to ridge-building, D_D is the divergence, and Δ is a function of the divergence and shear. These strain rates are computed by the dynamics scheme. The default value of C_s is 0.25.

Next, define $R_{\text{tot}} = \sum_{n=0}^N r_n$. This rate is related to R_{net} by

$$R_{\text{net}} = \left[a_{P0} + \sum_{n=1}^N a_{Pn} \left(1 - \frac{1}{k_n} \right) \right] R_{\text{tot}}. \quad (2.47)$$

Given R_{net} from Equation (2.46), we use Equation (2.47) to compute R_{tot} . Then the area ridged in category n is given by $a_{rn} = r_n \Delta t$, where $r_n = a_{Pn} R_{\text{tot}}$. The area of new ridges is a_{rn}/k_n , and the volume of new ridges is $a_{rn} h_n$ (since volume is conserved during ridging). We remove the ridging ice from category n and use Equations (2.41) and (2.42) (or (2.44) and (2.45)) to redistribute the ice among thicker categories.

Occasionally the ridging rate in thickness category n may be large enough to ridge the entire area a_n during a time interval less than Δt . In this case R_{tot} is reduced to the value that exactly ridges an area a_n during Δt . After each ridging iteration, the total fractional ice area a_i is computed. If $a_i > 1$, the ridging is repeated with a value of R_{net} sufficient to yield $a_i = 1$.

Two tracers for tracking the ridged ice area and volume are available. The actual tracers are for level (undeformed) ice area (*alvl*) and volume (*vlvl*), which are easier to implement for a couple of reasons: (1) ice ridged in a given thickness category is spread out among the rest of the categories, making it more difficult (and expensive) to track than the level ice remaining behind in the original category; (2) previously ridged ice may ridge again, so that simply adding a volume of freshly ridged ice to the volume of previously ridged ice in a grid cell may be inappropriate. Although the code currently only tracks level ice internally, both level ice and ridged ice are available for output. They are simply related:

$$\begin{aligned} a_{lvl} + a_{rdg} &= a_i, \\ v_{lvl} + v_{rdg} &= v_i. \end{aligned} \quad (2.48)$$

Level ice area fraction and volume increase with new ice formation and decrease steadily via ridging processes. Without the formation of new ice, level ice asymptotes to zero because we assume that both level ice and ridged ice ridge, in proportion to their fractional areas in a grid cell (in the spirit of the ridging calculation itself which does not prefer level ice over previously ridged ice).

The ice strength P may be computed in either of two ways. If the namelist parameter `kstrength = 0`, we use the strength formula from [19]:

$$P = P^* h \exp[-C(1 - a_i)], \quad (2.49)$$

where $P^* = 27,500 \text{ N/m}$ and $C = 20$ are empirical constants, and h is the mean ice thickness. Alternatively, setting `kstrength = 1` gives an ice strength closely related to the ridging scheme. Following [43], the strength is assumed proportional to the change in ice potential energy ΔE_P per unit area of compressive deformation. Given uniform ridge ITDs (`krdg_redist = 0`), we have

$$P = C_f C_p \beta \sum_{n=1}^{N_C} \left[-a_{Pn} h_n^2 + \frac{a_{Pn}}{k_n} \left(\frac{(H_n^{\max})^3 - (H_n^{\min})^3}{3(H_n^{\max} - H_n^{\min})} \right) \right], \quad (2.50)$$

where $C_P = (g/2)(\rho_i/\rho_w)(\rho_w - \rho_i)$, $\beta = R_{\text{tot}}/R_{\text{net}} > 1$ from Equation (2.47), and C_f is an empirical parameter that accounts for frictional energy dissipation. Following [12], we set $C_f = 17$. The first term in the summation is the potential energy of ridging ice, and the second, larger term is the potential energy of the resulting ridges. The factor of β is included because a_{Pn} is normalized with respect to the total area of ice ridging, not the net area removed. Recall that more than one unit area of ice must be ridged to reduce the net ice area by one unit. For exponential ridge ITDs (`krdg_redist = 1`), the ridge potential energy is modified:

$$P = C_f C_p \beta \sum_{n=1}^{N_C} \left[-a_{Pn} h_n^2 + \frac{a_{Pn}}{k_n} (H_{\min}^2 + 2H_{\min}\lambda + 2\lambda^2) \right] \quad (2.51)$$

The energy-based ice strength given by Equations (2.50) or (2.51) is more physically realistic than the strength given by Equation (2.49). However, use of Equation (2.49) is less likely to allow numerical instability at a given resolution and time step. See [32] for more details.

2.6 Thermodynamics

The current Icepack version includes three thermodynamics options, the “zero-layer” thermodynamics of [46] (`ktherm = 0`), the Bitz and Lipscomb model [6] (`ktherm = 1`) that assumes a fixed salinity profile, and a “mushy” formulation (`ktherm = 2`) in which salinity evolves [53]. For each thickness category, Icepack computes changes in the ice and snow thickness and vertical temperature profile resulting from radiative, turbulent, and conductive heat fluxes. The ice has a temperature-dependent specific heat to simulate the effect of brine pocket melting and freezing, for `ktherm = 1` and 2.

Each thickness category n in each grid cell is treated as a horizontally uniform column with ice thickness $h_{in} = v_{in}/a_{in}$ and snow thickness $h_{sn} = v_{sn}/a_{in}$. (Henceforth we omit the category index n .) Each column is divided into N_i ice layers of thickness $\Delta h_i = h_i/N_i$ and N_s snow layers of thickness $\Delta h_s = h_s/N_s$. The surface temperature (i.e., the temperature of ice or snow at the interface with the atmosphere) is T_{sf} , which cannot exceed 0°C . The temperature at the midpoint of the snow layer is T_s , and the midpoint ice layer temperatures are T_{ik} , where k ranges from 1 to N_i . The temperature at the bottom of the ice is held at T_f , the freezing temperature of the ocean mixed layer. All temperatures are in degrees Celsius unless stated otherwise.

Each ice layer has an enthalpy q_{ik} , defined as the negative of the energy required to melt a unit volume of ice and raise its temperature to 0°C . Because of internal melting and freezing in brine pockets, the ice enthalpy depends on the brine pocket volume and is a function of temperature and salinity. We can also define a snow enthalpy q_s , which depends on temperature alone.

Given surface forcing at the atmosphere–ice and ice–ocean interfaces along with the ice and snow thicknesses and temperatures/enthalpies at time m , the thermodynamic model advances these quantities to time $m + 1$ (`ktherm = 2` also advances salinity). The calculation proceeds in two steps. First we solve a set of equations for the new temperatures, as discussed in the [New temperatures](#) section. Then we compute the melting, if any, of ice or snow at the top surface, and the growth or melting of ice at the bottom surface, as described in the [Growth and melting](#) section. We begin by describing the melt ponds and surface forcing parameterizations, which are closely related to the ice and snow surface temperatures.

2.6.1 Melt ponds

Three explicit melt pond parameterizations are available in Icepack, and all must use the delta-Eddington radiation scheme, described below. The ccsm3 shortwave parameterization incorporates melt ponds implicitly by adjusting the albedo based on surface conditions.

For each of the three explicit parameterizations, a volume ΔV_{melt} of melt water produced on a given category may be added to the melt pond liquid volume:

$$\Delta V_{melt} = \frac{r}{\rho_w} (\rho_i \Delta h_i + \rho_s \Delta h_s + F_{rain} \Delta t) a_i, \quad (2.52)$$

where

$$r = r_{min} + (r_{max} - r_{min}) a_i \quad (2.53)$$

is the fraction of the total melt water available that is added to the ponds, ρ_i and ρ_s are ice and snow densities, Δh_i and Δh_s are the thicknesses of ice and snow that melted, and F_{rain} is the rainfall rate. Namelist parameters are set for the level-ice (`tr_pond_lvl`) parameterization; in the cesm and topo pond schemes the standard values of r_{max} and r_{min} are 0.7 and 0.15, respectively.

Radiatively, the surface of an ice category is divided into fractions of snow, pond and bare ice. In these melt pond schemes, the actual pond area and depth are maintained throughout the simulation according to the physical processes acting on it. However, snow on the sea ice and pond ice may shield the pond and ice below from solar radiation. These processes do not alter the actual pond volume; instead they are used to define an “effective pond fraction” (and likewise, effective pond depth, snow fraction and snow depth) used only for the shortwave radiation calculation.

In addition to the physical processes discussed below, tracer equations and definitions for melt ponds are also described in the *Tracers* section.

CESM formulation (`tr_pond_cesm = true`)

Melt pond area and thickness tracers are carried on each ice thickness category as in the *Tracers* section. Defined simply as the product of pond area, a_p , and depth, h_p , the melt pond volume, V_p , grows through addition of ice or snow melt water or rain water, and shrinks when the ice surface temperature becomes cold,

$$\begin{aligned} \text{pond growth : } V'_p &= V_p(t) + \Delta V_{melt}, \\ \text{pond contraction : } V_p(t + \Delta t) &= V'_p \exp \left[r_2 \left(\frac{\max(T_p - T_{sfc}, 0)}{T_p} \right) \right], \end{aligned} \quad (2.54)$$

where dh_i and dh_s represent ice and snow melt at the top surface of each thickness category and $r_2 = 0.01$. Here, T_p is a reference temperature equal to -2°C . Pond depth is assumed to be a linear function of the pond fraction ($h_p = \delta_p a_p$) and is limited by the category ice thickness ($h_p \leq 0.9 h_i$). The pond shape (`pondaspect`) $\delta_p = 0.8$ in the standard CESM pond configuration. The area and thickness are computed according to the assumed pond shape, and the pond area is then reduced in the presence of snow for the radiation calculation. Ponds are allowed only on ice at least 1 cm thick. This formulation differs slightly from that documented in [21].

Topographic formulation (`tr_pond_topo = true`)

The principle concept of this scheme is that melt water runs downhill under the influence of gravity and collects on sea ice with increasing surface height starting at the lowest height [13][14][15]. Thus, the topography of the ice cover plays a crucial role in determining the melt pond cover. However, Icepack does not explicitly represent the topography of sea ice. Therefore, we split the existing ice thickness distribution function into a surface height and basal depth distribution assuming that each sea ice thickness category is in hydrostatic equilibrium at the beginning of the melt season. We then calculate the position of sea level assuming that the ice in the whole grid cell is rigid and in hydrostatic equilibrium.




Fig. 2.3: Melt Ponds

Figure [Melt Ponds](#) illustrates (a) Schematic illustration of the relationship between the height of the pond surface $h_{pnd,tot}$, the volume of water V_{Pk} required to completely fill up to category k , the volume of water $V_P - V_{Pk}$, and the depth to which this fills category $k + 1$. Ice and snow areas a_i and a_s are also depicted. The volume calculation takes account of the presence of snow, which may be partially or completely saturated. (b) Schematic illustration indicating pond surface height $h_{pnd,tot}$ and sea level h_{sl} measured with respect to the thinnest surface height category h_{i1} , the submerged portion of the floe h_{sub} , and hydraulic head ΔH . A positive hydraulic head (pond surface above sea level) will flush melt water through the sea ice into the ocean; a negative hydraulic head can drive percolation of sea water onto the ice surface. Here, $\alpha = 0.6$ and $\beta = 0.4$ are the surface height and basal depth distribution fractions. The height of the steps is the height of the ice above the reference level, and the width of the steps is the area of ice of that height. The illustration does not imply a particular assumed topography, rather it is assumed that all thickness categories are present at the sub-grid scale so that water will always flow to the lowest surface height class.

Once a volume of water is produced from ice and snow melting, we calculate the number of ice categories covered by water. At each time step, we construct a list of volumes of water $\{V_{P1}, V_{P2}, \dots, V_{P,k-1}, V_{Pk}, V_{P,k+1}, \dots\}$, where V_{Pk} is the volume of water required to completely cover the ice and snow in the surface height categories from $i = 1$ to $i = k$. The volume V_{Pk} is defined so that if the volume of water V_P is such that $V_{Pk} < V_P < V_{P,k+1}$ then the snow and ice in categories $n = 1$ to $n = k + 1$ are covered in melt water. Figure [Melt Ponds](#) (a) depicts the areas covered in melt water and saturated snow on the surface height (rather than thickness) categories $h_{top,k}$. Note in the code, we assume that $h_{top,n}/h_{in} = 0.6$ (an arbitrary choice). The fractional area of the n th category covered in snow is a_{sn} . The volume V_{P1} , which is the region with vertical hatching, is the volume of water required to completely fill the first thickness category, so that any extra melt water must occupy the second thickness category, and it is given by the expression

$$V_{P1} = a_{i1}(h_{top,2} - h_{top,1}) - a_{s1}a_{i1}h_{s1}(1 - V_{sw}), \quad (2.55)$$

where V_{sw} is the fraction of the snow volume that can be occupied by water, and h_{s1} is the snow depth on ice height class 1. In a similar way, the volume required to fill the first and second surface categories, V_{P2} , is given by

$$V_{P2} = a_{i1}(h_{top,3} - h_{top,2}) + a_{i2}(h_{top,3} - h_{top,2}) - a_{s2}a_{i2}h_{s2}(1 - V_{sw}) + V_{P1}. \quad (2.56)$$

The general expression for volume V_{Pk} is given by

$$V_{Pk} = \sum_{m=0}^k a_{im}(h_{top,k+1} - h_{top,k}) - a_{sk}a_{ik}h_{sk}(1 - V_{sw}) + \sum_{m=0}^{k-1} V_{Pm}. \quad (2.57)$$

(Note that we have implicitly assumed that $h_{si} < h_{top,k+1} - h_{top,k}$ for all k .) No melt water can be stored on the thickest ice thickness category. If the melt water volume exceeds the volume calculated above, the remaining melt water is released to the ocean.

At each time step, the pond height above the level of the thinnest surface height class, that is, the maximum pond depth, is diagnosed from the list of volumes V_{Pk} . In particular, if the total volume of melt water V_P is such that $V_{Pk} < V_P < V_{P,k+1}$ then the pond height $h_{pnd,tot}$ is

$$h_{pnd,tot} = h_{par} + h_{top,k} - h_{top,1}, \quad (2.58)$$

where h_{par} is the height of the pond above the level of the ice in class k and partially fills the volume between $V_{P,k}$ and $V_{P,k+1}$. From Figure [Melt Ponds](#) (a) we see that $h_{top,k} - h_{top,1}$ is the height of the melt water, which has volume V_{Pk} , which completely fills the surface categories up to category k . The remaining volume, $V_P - V_{Pk}$, partially fills category $k + 1$ to the height h_{par} and there are two cases to consider: either the snow cover on category $k + 1$, with height $h_{s,k+1}$, is completely covered in melt water (i.e., $h_{par} > h_{s,k+1}$), or it is not (i.e., $h_{par} \leq h_{s,k+1}$). From conservation of volume, we see from Figure [Melt Ponds](#) (a) that for an incompletely to completely saturated snow cover on surface ice class $k + 1$,

$$V_P - V_{Pk} = h_{par} \left(\sum_{m=1}^k a_{ik} + a_{i,k+1}(1 - a_{s,k+1}) + a_{i,k+1}a_{s,k+1}V_{sw} \right) \quad \text{for } h_{par} \leq h_{s,k+1}, \quad (2.59)$$

and for a saturated snow cover with water on top of the snow on surface ice class $k + 1$,

$$V_P - V_{Pk} = h_{par} \left(\sum_{m=1}^k a_{ik} + a_{i,k+1}(1 - a_{s,k+1}) \right) + a_{i,k+1}a_{s,k+1}V_{sw}h_{s,k+1} \quad (2.60)$$

$$+ a_{i,k+1}a_{s,k+1}(h_{par} - h_{s,k+1}) \quad \text{for } h_{par} > h_{s,k+1}.$$

As the melting season progresses, not only does melt water accumulate upon the upper surface of the sea ice, but the sea ice beneath the melt water becomes more porous owing to a reduction in solid fraction [10]. The hydraulic head of melt water on sea ice (i.e., its height above sea level) drives flushing of melt water through the porous sea ice and into the underlying ocean. The mushy thermodynamics scheme ($ktherm = 2$) handles flushing. For $ktherm \neq 2$ we model the vertical flushing rate using Darcy's law for flow through a porous medium

$$w = -\frac{\Pi_v}{\mu} \rho_o g \frac{\Delta H}{h_i}, \quad (2.61)$$

where w is the vertical mass flux per unit perpendicular cross-sectional area (i.e., the vertical component of the Darcy velocity), Π_v is the vertical component of the permeability tensor (assumed to be isotropic in the horizontal), μ is the viscosity of water, ρ_o is the ocean density, g is gravitational acceleration, ΔH is the the hydraulic head, and h_i is the thickness of the ice through which the pond flushes. As proposed by [18] the vertical permeability of sea ice can be calculated from the liquid fraction ϕ :

$$\Pi_v = 3 \times 10^{-8} \phi^3 \text{m}^2. \quad (2.62)$$

Since the solid fraction varies throughout the depth of the sea ice, so does the permeability. The rate of vertical drainage is determined by the lowest (least permeable) layer, corresponding to the highest solid fraction. From the equations describing sea ice as a mushy layer [11], the solid fraction is determined by:

$$\phi = \frac{c_i - S}{c_i - S_{br}(T)}, \quad (2.63)$$

where S is the bulk salinity of the ice, $S_{br}(T)$ is the concentration of salt in the brine at temperature T and c_i is the concentration of salt in the ice crystals (set to zero).

The hydraulic head is given by the difference in height between the upper surface of the melt pond $h_{pnd,tot}$ and the sea level h_{sl} . The value of the sea level h_{sl} is calculated from

$$h_{sl} = h_{sub} - 0.4 \sum_{n=1}^N a_{in} h_{in} - \beta h_{i1}, \quad (2.64)$$

where $0.4 \sum_{n=1}^N a_{in} h_{in}$ is the mean thickness of the basal depth classes, and h_{sub} is the depth of the submerged portion of the floe. Figure [Melt Ponds](#) (b) depicts the relationship between the hydraulic head and the depths and heights that appear in Equation (2.64). The depth of the submerged portion of the floe is determined from hydrostatic equilibrium to be

$$h_{sub} = \frac{\rho_m}{\rho_w} V_P + \frac{\rho_s}{\rho_w} V_s + \frac{\rho_i}{\rho_w} V_i, \quad (2.65)$$

where ρ_m is the density of melt water, V_P is the total pond volume, V_s is the total snow volume, and V_i is the total ice volume.

When the surface energy balance is negative, a layer of ice is formed at the upper surface of the ponds. The rate of growth of the ice lid is given by the Stefan energy budget at the lid-pond interface

$$\rho_i L_0 \frac{dh_{ipnd}}{dt} = k_i \frac{\partial T_i}{\partial z} - k_p \frac{\partial T_p}{\partial z}, \quad (2.66)$$

where L_0 is the latent heat of fusion of pure ice per unit volume, T_i and T_p are the ice surface and pond temperatures, and k_i and k_p are the thermal conductivity of the ice lid and pond respectively. The second term on the right hand-side

is close to zero since the pond is almost uniformly at the freezing temperature [49]. Approximating the temperature gradient in the ice lid as linear, the Stefan condition yields the classic Stefan solution for ice lid depth

$$h_{ipnd} = \sqrt{\frac{2k_i}{\rho_s L} \Delta T_i t}, \quad (2.67)$$

where ΔT is the temperature difference between the top and the bottom of the lid. Depending on the surface flux conditions the ice lid can grow, partially melt, or melt completely. Provided that the ice lid is thinner than a critical lid depth (1 cm is suggested) then the pond is regarded as effective, i.e. the pond affects the optical properties of the ice cover. Effective pond area and pond depth for each thickness category are passed to the radiation scheme for calculating albedo. Note that once the ice lid has exceeded the critical thickness, snow may accumulate on the lid causing a substantial increase in albedo. In the current CICE model, melt ponds only affect the thermodynamics of the ice through the albedo. To conserve energy, the ice lid is dismissed once the pond is completely refrozen.

As the sea ice area shrinks due to melting and ridging, the pond volume over the lost area is released to the ocean immediately. In [14], the pond volume was carried as an ice area tracer, but in [15] and here, pond area and thickness are carried as separate tracers, as in the *Tracers* section.

Unlike the cesm and level-ice melt pond schemes, the liquid pond water in the topo parameterization is not necessarily virtual; it can be withheld from being passed to the ocean model until the ponds drain by setting the namelist variable `l_mpond_fresh = .true.` The refrozen pond lids are still virtual. Extra code needed to track and enforce conservation of water has been added to **icepack_itd.F90** (subroutine *zap_small_areas*), **icepack_mechred.F90** (subroutine *ridge_shift*), **icepack_therm_itd.F90** (subroutines *linear_itd* and *lateral_melt*), and **icepack_therm_vertical.F90** (subroutine *thermo_vertical*), along with global diagnostics in **icedrv_diagnostics.F90**.

Level-ice formulation (`tr_pond_lv1 = true`)

This meltpond parameterization represents a combination of ideas from the empirical CESM melt pond scheme and the topo approach, and is documented in [23]. The ponds evolve according to physically based process descriptions, assuming a thickness-area ratio for changes in pond volume. A novel aspect of the new scheme is that the ponds are carried as tracers on the level (undeformed) ice area of each thickness category, thus limiting their spatial extent based on the simulated sea ice topography. This limiting is meant to approximate the horizontal drainage of melt water into depressions in ice floes. (The primary difference between the level-ice and topo meltpond parameterizations lies in how sea ice topography is taken into account when determining the areal coverage of ponds.) Infiltration of the snow by melt water postpones the appearance of ponds and the subsequent acceleration of melting through albedo feedback, while snow on top of refrozen pond ice also reduces the ponds' effect on the radiation budget.

Melt pond processes, described in more detail below, include addition of liquid water from rain, melting snow and melting surface ice, drainage of pond water when its weight pushes the ice surface below sea level or when the ice interior becomes permeable, and refreezing of the pond water. If snow falls after a layer of ice has formed on the ponds, the snow may block sunlight from reaching the ponds below. When melt water forms with snow still on the ice, the water is assumed to infiltrate the snow. If there is enough water to fill the air spaces within the snowpack, then the pond becomes visible above the snow, thus decreasing the albedo and ultimately causing the snow to melt faster. The albedo also decreases as snow depth decreases, and thus a thin layer of snow remaining above a pond-saturated layer of snow will have a lower albedo than if the melt water were not present.

The level-ice formulation assumes a thickness-area ratio for *changes* in pond volume, while the CESM scheme assumes this ratio for the total pond volume. Pond volume changes are distributed as changes to the area and to the depth of the ponds using an assumed aspect ratio, or shape, given by the parameter δ_p (`pndaspect`), $\delta_p = \Delta h_p / \Delta a_p$ and $\Delta V = \Delta h_p \Delta a_p = \delta_p \Delta a_p^2 = \Delta h_p^2 / \delta_p$. Here, $a_p = a_{pnd} a_{lvl}$, the mean pond area over the ice.

Given the ice velocity \mathbf{u} , conservation equations for level ice fraction $a_{lvl} a_i$, pond area fraction $a_{pnd} a_{lvl} a_i$, pond volume $h_{pnd} a_{pnd} a_{lvl} a_i$ and pond ice volume $h_{ipnd} a_{pnd} a_{lvl} a_i$ are

$$\frac{\partial}{\partial t} (a_{lvl} a_i) + \nabla \cdot (a_{lvl} a_i \mathbf{u}) = 0, \quad (2.68)$$

$$\frac{\partial}{\partial t}(a_{pnd}a_{lvl}a_i) + \nabla \cdot (a_{pnd}a_{lvl}a_i \mathbf{u}) = 0, \quad (2.69)$$

$$\frac{\partial}{\partial t}(h_{pnd}a_{pnd}a_{lvl}a_i) + \nabla \cdot (h_{pnd}a_{pnd}a_{lvl}a_i \mathbf{u}) = 0, \quad (2.70)$$

$$\frac{\partial}{\partial t}(h_{ipnd}a_{pnd}a_{lvl}a_i) + \nabla \cdot (h_{ipnd}a_{pnd}a_{lvl}a_i \mathbf{u}) = 0. \quad (2.71)$$

(We have dropped the category subscript here, for clarity.) Equations (2.70) and (2.71) express conservation of melt pond volume and pond ice volume, but in this form highlight that the quantities tracked in the code are the tracers h_{pnd} and h_{ipnd} , pond depth and pond ice thickness. Likewise, the level ice fraction a_{lvl} is a tracer on ice area fraction (Equation (2.68)), and pond fraction a_{pnd} is a tracer on level ice (Equation (2.69)).

Pond ice. The ponds are assumed to be well mixed fresh water, and therefore their temperature is 0°C. If the air temperature is cold enough, a layer of clear ice may form on top of the ponds. There are currently three options in the code for refreezing the pond ice. Only option A tracks the thickness of the lid ice using the tracer h_{ipnd} and includes the radiative effect of snow on top of the lid.

A. The `frzpond = 'hlid'` option uses a Stefan approximation for growth of fresh ice and is invoked only when $\Delta V_{melt} = 0$.

The basic thermodynamic equation governing ice growth is

$$\rho_i L \frac{\partial h_i}{\partial t} = k_i \frac{\partial T_i}{\partial z} \sim k_i \frac{\Delta T}{h_i} \quad (2.72)$$

assuming a linear temperature profile through the ice thickness h_i . In discrete form, the solution is

$$\Delta h_i = \begin{cases} \sqrt{\beta \Delta t}/2 & \text{if } h_i = 0 \\ \beta \Delta t / 2h_i & \text{if } h_i > 0, \end{cases} \quad (2.73)$$

where

$$\beta = \frac{2k_i \Delta T}{\rho_i L}. \quad (2.74)$$

When $\Delta V_{melt} > 0$, any existing pond ice may also melt. In this case,

$$\Delta h_i = -\min \left(\frac{\max(F_o, 0) \Delta t}{\rho_i L}, h_i \right), \quad (2.75)$$

where F_o is the net downward surface flux.

In either case, the change in pond volume associated with growth or melt of pond ice is

$$\Delta V_{frz} = -\Delta h_i a_{pnd} a_{lvl} a_i \rho_i / \rho_0, \quad (2.76)$$

where ρ_0 is the density of fresh water.

B. The `frzpond = 'cesm'` option uses the same empirical function as in the CESM melt pond parameterization.

Radiative effects. Freshwater ice that has formed on top of a melt pond is assumed to be perfectly clear. Snow may accumulate on top of the pond ice, however, shading the pond and ice below. The depth of the snow on the pond ice is initialized as $h_{ps}^0 = F_{snow} \Delta t$ at the first snowfall after the pond ice forms. From that time until either the pond ice or the pond snow disappears, the pond snow depth tracks the depth of snow on sea ice (h_s) using a constant difference Δ . As h_s melts, $h_{ps} = h_s - \Delta$ will be reduced to zero eventually, at which time the pond ice is fully uncovered and shortwave radiation passes through.

To prevent a sudden change in the shortwave reaching the sea ice (which can prevent the thermodynamics from converging), thin layers of snow on pond ice are assumed to be patchy, thus allowing the shortwave flux to increase gradually as the layer thins. This is done using the same parameterization for patchy snow as is used elsewhere in Icepack, but with its own parameter h_{s1} :

$$a_{pnd}^{eff} = (1 - \min(h_{ps}/h_{s1}, 1)) a_{pnd} a_{lvl}. \quad (2.77)$$

If any of the pond ice melts, the radiative flux allowed to pass through the ice is reduced by the (roughly) equivalent flux required to melt that ice. This is accomplished (approximately) with $a_{pnd}^{eff} = (1 - f_{frac}) a_{pnd} a_{lvl}$, where (see Equation (2.75))

$$f_{frac} = \min\left(-\frac{\rho_i L \Delta h_i}{F_o \Delta t}, 1\right). \quad (2.78)$$

Snow infiltration by pond water. If there is snow on top of the sea ice, melt water may infiltrate the snow. It is a “virtual process” that affects the model’s thermodynamics through the input parameters of the radiation scheme; it does not melt the snow or affect the snow heat content.

A snow pack is considered saturated when its percentage of liquid water content is greater or equal to 15% (Sturm and others, 2009). We assume that if the volume fraction of retained melt water to total liquid content

$$r_p = \frac{V_p}{V_p + V_s \rho_s / \rho_0} < 0.15, \quad (2.79)$$

then effectively there are no meltponds present, that is, $a_{pnd}^{eff} = h_{pnd}^{eff} = 0$. Otherwise, we assume that the snowpack is saturated with liquid water.

We assume that all of the liquid water accumulates at the base of the snow pack and would eventually melt the surrounding snow. Two configurations are therefore possible, (1) the top of the liquid lies below the snow surface and (2) the liquid water volume overtops the snow, and all of the snow is assumed to have melted into the pond. The volume of void space within the snow that can be filled with liquid melt water is

$$V_{mx} = h_{mx} a_p = \left(\frac{\rho_0 - \rho_s}{\rho_0}\right) h_s a_p, \quad (2.80)$$

and we compare V_p with V_{mx} .

Case 1: For $V_p < V_{mx}$, we define V_p^{eff} to be the volume of void space filled by the volume V_p of melt water: $\rho_0 V_p = (\rho_0 - \rho_s) V_p^{eff}$, or in terms of depths,

$$h_p^{eff} = \left(\frac{\rho_0}{\rho_0 - \rho_s}\right) h_{pnd}. \quad (2.81)$$

The liquid water under the snow layer is not visible and therefore the ponds themselves have no direct impact on the radiation ($a_{pnd}^{eff} = h_{pnd}^{eff} = 0$), but the effective snow thickness used for the radiation scheme is reduced to

$$h_s^{eff} = h_s - h_p^{eff} a_p = h_s - \frac{\rho_0}{\rho_0 - \rho_s} h_{pnd} a_p. \quad (2.82)$$

Here, the factor $a_p = a_{pnd} a_{lvl}$ averages the reduced snow depth over the ponds with the full snow depth over the remainder of the ice; that is, $h_s^{eff} = h_s(1 - a_p) + (h_s - h_p^{eff}) a_p$.

Case 2: Similarly, for $V_p \geq V_{mx}$, the total mass in the liquid is $\rho_0 V_p + \rho_s V_s = \rho_0 V_p^{eff}$, or

$$h_p^{eff} = \frac{\rho_0 h_{pnd} + \rho_s h_s}{\rho_0}. \quad (2.83)$$

Thus the effective depth of the pond is the depth of the whole slush layer h_p^{eff} . In this case, $a_{pnd}^{eff} = a_{pnd} a_{lvl}$.

Drainage. A portion $1 - r$ of the available melt water drains immediately into the ocean. Once the volume changes described above have been applied and the resulting pond area and depth calculated, the pond depth may be further reduced if the top surface of the ice would be below sea level or if the sea ice becomes permeable.

We require that the sea ice surface remain at or above sea level. If the weight of the pond water would push the mean ice–snow interface of a thickness category below sea level, some or all of the pond water is removed to bring the interface back to sea level via Archimedes’ Principle written in terms of the draft d ,

$$\rho_i h_i + \rho_s h_s + \rho_0 h_p = \rho_w d \leq \rho_w h_i. \quad (2.84)$$

There is a separate freeboard calculation in the thermodynamics which considers only the ice and snow and converts flooded snow to sea ice. Because the current melt ponds are “virtual” in the sense that they only have a radiative influence, we do not allow the pond mass to change the sea ice and snow masses at this time, although this issue may need to be reconsidered in the future, especially for the Antarctic.

The mushy thermodynamics scheme ($ktherm = 2$) handles flushing. For $ktherm \neq 2$, the permeability of the sea ice is calculated using the internal ice temperatures T_i (computed from the enthalpies as in the sea ice thermodynamics). The brine salinity and liquid fraction are given by [39] [eq 3.6] $S_{br} = 1/(10^{-3} - 0.054/T_i)$ and $\phi = S/S_{br}$, where S is the bulk salinity of the combined ice and brine. The ice is considered permeable if $\phi \geq 0.05$ with a permeability of $p = 3 \times 10^{-8} \min(\phi^3)$ (the minimum being taken over all of the ice layers). A hydraulic pressure head is computed as $P = g\rho_w \Delta h$ where Δh is the height of the pond and sea ice above sea level. Then the volume of water drained is given by

$$\Delta V_{perm} = -a_{pnd} \min \left(h_{pnd}, \frac{p P d_p \Delta t}{\mu h_i} \right), \quad (2.85)$$

where d_p is a scaling factor (dpscale), and $\mu = 1.79 \times 10^{-3} \text{ kg m}^{-1} \text{ s}^{-1}$ is the dynamic viscosity.

Conservation elsewhere. When ice ridges and when new ice forms in open water, the level ice area changes and ponds must be handled appropriately. For example, when sea ice deforms, some of the level ice is transformed into ridged ice. We assume that pond water (and ice) on the portion of level ice that ridges is lost to the ocean. All of the tracer volumes are altered at this point in the code, even though h_{pnd} and h_{ipnd} should not change; compensating factors in the tracer volumes cancel out (subroutine *ridge_shift* in **icepack_mechred.F90**).

When new ice forms in open water, level ice is added to the existing sea ice, but the new level ice does not yet have ponds on top of it. Therefore the fractional coverage of ponds on level ice decreases (thicknesses are unchanged). This is accomplished in **icepack_therm_itd.F90** (subroutine *add_new_ice*) by maintaining the same mean pond area in a grid cell after the addition of new ice,

$$a'_{pnd}(a_{lvl} + \Delta a_{lvl})(a_i + \Delta a_i) = a_{pnd} a_{lvl} a_i, \quad (2.86)$$

and solving for the new pond area tracer a'_{pnd} given the newly formed ice area $\Delta a_i = \Delta a_{lvl}$.

2.6.2 Thermodynamic surface forcing balance

The net surface energy flux from the atmosphere to the ice (with all fluxes defined as positive downward) is

$$F_0 = F_s + F_l + F_{L\downarrow} + F_{L\uparrow} + (1 - \alpha)(1 - i_0)F_{sw}, \quad (2.87)$$

where F_s is the sensible heat flux, F_l is the latent heat flux, $F_{L\downarrow}$ is the incoming longwave flux, $F_{L\uparrow}$ is the outgoing longwave flux, F_{sw} is the incoming shortwave flux, α is the shortwave albedo, and i_0 is the fraction of absorbed shortwave flux that penetrates into the ice. The albedo may be altered by the presence of melt ponds. Each of the explicit melt pond parameterizations (CESM, topo and level-ice ponds) should be used in conjunction with the Delta-Eddington shortwave scheme, described below.

Shortwave radiation: Delta-Eddington

Two methods for computing albedo and shortwave fluxes are available, the “ccsm3” method, described below, and a multiple scattering radiative transfer scheme that uses a Delta-Eddington approach. “Inherent” optical properties (IOPs) for snow and sea ice, such as extinction coefficient and single scattering albedo, are prescribed based on physical measurements; reflected, absorbed and transmitted shortwave radiation (“apparent” optical properties) are then computed for each snow and ice layer in a self-consistent manner. Absorptive effects of inclusions in the ice/snow matrix such as dust and algae can also be included, along with radiative treatment of melt ponds and other changes in physical properties, for example granularization associated with snow aging. The Delta-Eddington formulation is described in detail in [7]. Since publication of this technical paper, a number of improvements have been made to the Delta-Eddington scheme, including a surface scattering layer and internal shortwave absorption for snow, generalization for multiple snow layers and more than four layers of ice, and updated IOP values.

The namelist parameters R_{ice} and R_{pnd} adjust the albedo of bare or ponded ice by the product of the namelist value and one standard deviation. For example, if $R_{ice} = 0.1$, the albedo increases by 0.1σ . Similarly, setting $R_{snw} = 0.1$ decreases the snow grain radius by 0.1σ (thus increasing the albedo). Two additional tuning parameters are available for this scheme, dT_{melt} and $rsnw_{melt}$. dT_{melt} is the temperature change needed for a change in snow grain radius from non-melting to melting, and $rsnw_{melt}$ is the maximum snow grain radius when melting. An absorption coefficient for algae (k_{alg}) may also be set. See [7] for details; the CESM melt pond and Delta-Eddington parameterizations are further explained and validated in [21].

Shortwave radiation: CCSM3

In the parameterization used in the previous version of the Community Climate System Model (CCSM3), the albedo depends on the temperature and thickness of ice and snow and on the spectral distribution of the incoming solar radiation. Albedo parameters have been chosen to fit observations from the SHEBA field experiment. For $T_{sf} < -1^\circ C$ and $h_i > h_{ahmax}$, the bare ice albedo is 0.78 for visible wavelengths ($< 700nm$) and 0.36 for near IR wavelengths ($> 700nm$). As h_i decreases from $ahmax$ to zero, the ice albedo decreases smoothly (using an arctangent function) to the ocean albedo, 0.06. The ice albedo in both spectral bands decreases by 0.075 as T_{sf} rises from $-1^\circ C$ to $0^\circ C$. The albedo of cold snow ($T_{sf} < -1^\circ C$) is 0.98 for visible wavelengths and 0.70 for near IR wavelengths. The visible snow albedo decreases by 0.10 and the near IR albedo by 0.15 as T_{sf} increases from $-1^\circ C$ to $0^\circ C$. The total albedo is an area-weighted average of the ice and snow albedos, where the fractional snow-covered area is

$$f_{snow} = \frac{h_s}{h_s + h_{snowpatch}}, \quad (2.88)$$


and $h_{snowpatch} = 0.02$ m. The envelope of albedo values is shown in Figure [Albedo](#). This albedo formulation incorporates the effects of melt ponds implicitly; the explicit melt pond parameterization is not used in this case.

Figure [Albedo](#) illustrates Albedo as a function of ice thickness and temperature, for the two extrema in snow depth, for the ccsm3 shortwave option. Maximum snow depth is computed based on Archimedes’ Principle for the given ice thickness. These curves represent the envelope of possible albedo values.

The net absorbed shortwave flux is $F_{swabs} = \sum (1 - \alpha_j) F_{sw\downarrow}$, where the summation is over four radiative categories (direct and diffuse visible, direct and diffuse near infrared). The flux penetrating into the ice is $I_0 = i_0 F_{swabs}$, where $i_0 = 0.70(1 - f_{snow})$ for visible radiation and $i_0 = 0$ for near IR. Radiation penetrating into the ice is attenuated according to Beer’s Law:

$$I(z) = I_0 \exp(-\kappa_i z), \quad (2.89)$$

where $I(z)$ is the shortwave flux that reaches depth z beneath the surface without being absorbed, and κ_i is the bulk extinction coefficient for solar radiation in ice, set to 1.4 m^{-1} for visible wavelengths [9]. A fraction $\exp(-\kappa_i h_i)$ of the penetrating solar radiation passes through the ice to the ocean ($F_{sw\downarrow}$).

Fig. 2.4: *Albedo*

Longwave radiation, turbulent fluxes

While incoming shortwave and longwave radiation are obtained from the atmosphere, outgoing longwave radiation and the turbulent heat fluxes are derived quantities. Outgoing longwave takes the standard blackbody form, $F_{L\uparrow} = \epsilon \sigma (T_{sf}^K)^4$, where $\epsilon = 0.95$ is the emissivity of snow or ice, σ is the Stefan-Boltzmann constant and T_{sf}^K is the surface temperature in Kelvin. (The longwave fluxes are partitioned such that $\epsilon F_{L\downarrow}$ is absorbed at the surface, the remaining $(1 - \epsilon) F_{L\downarrow}$ being returned to the atmosphere via $F_{L\uparrow}$.) The sensible heat flux is proportional to the difference between air potential temperature and the surface temperature of the snow or snow-free ice,

$$F_s = C_s (\Theta_a - T_{sf}^K). \quad (2.90)$$

C_s and C_l (below) are nonlinear turbulent heat transfer coefficients described in the [Atmosphere](#) section. Similarly, the latent heat flux is proportional to the difference between Q_a and the surface saturation specific humidity Q_{sf} :

$$\begin{aligned} F_l &= C_l (Q_a - Q_{sf}), \\ Q_{sf} &= (q_1 / \rho_a) \exp(-q_2 / T_{sf}^K), \end{aligned}$$

where $q_1 = 1.16378 \times 10^7 \text{ kg/m}^3$, $q_2 = 5897.8 \text{ K}$, T_{sf}^K is the surface temperature in Kelvin, and ρ_a is the surface air density.

The net downward heat flux from the ice to the ocean is given by [\[36\]](#):

$$F_{bot} = -\rho_w c_w c_h u_* (T_w - T_f), \quad (2.91)$$

where ρ_w is the density of seawater, c_w is the specific heat of seawater, $c_h = 0.006$ is a heat transfer coefficient, $u_* = \sqrt{|\vec{\tau}_w| / \rho_w}$ is the friction velocity, and T_w is the sea surface temperature. A minimum value of u_* is available; we recommend $u_{* \min} = 5 \times 10^{-4} \text{ m/s}$, but the optimal value may depend on the ocean forcing used and can be as low as 0.

F_{bot} is limited by the total amount of heat available from the ocean, F_{frzmlt} . Additional heat, F_{side} , is used to melt the ice laterally following [\[37\]](#) and [\[48\]](#). F_{bot} and the fraction of ice melting laterally are scaled so that $F_{bot} + F_{side} \geq F_{frzmlt}$ in the case that $F_{frzmlt} < 0$ (melting; see [Growth and melting](#)).

2.6.3 New temperatures

Zero-layer thermodynamics (`kt herm = 0`)

An option for zero-layer thermodynamics [\[46\]](#) is available in this version of Icepack by setting the namelist parameter `kt herm` to 0 and changing the number of ice layers, `nilyr`, in `icedrv_domain_size.F90` to 1. In the zero-layer case, the ice is fresh and the thermodynamic calculations are much simpler than in the other configurations, which we describe here.

Bitz and Lipscomb thermodynamics (`kt herm = 1`)

The “BL99” thermodynamic sea ice model is based on [\[38\]](#) and [\[6\]](#), and is described more fully in [\[30\]](#). The vertical salinity profile is prescribed and is unchanging in time. The snow is assumed to be fresh, and the midpoint salinity S_{ik} in each ice layer is given by

$$S_{ik} = \frac{1}{2} S_{\max} [1 - \cos(\pi z^{(\frac{a}{z+b})})], \quad (2.92)$$

where $z \equiv (k - 1/2)/N_i$, $S_{\max} = 3.2 \text{ ppt}$, and $a = 0.407$ and $b = 0.573$ are determined from a least-squares fit to the salinity profile observed in multiyear sea ice by [\[45\]](#). This profile varies from $S = 0$ at the top surface ($z = 0$) to $S = S_{\max}$ at the bottom surface ($z = 1$) and is similar to that used by [\[38\]](#). Equation (2.92) is fairly accurate for ice

that has drained at the top surface due to summer melting. It is not a good approximation for cold first-year ice, which has a more vertically uniform salinity because it has not yet drained. However, the effects of salinity on heat capacity are small for temperatures well below freezing, so the salinity error does not lead to significant temperature errors.

Temperature updates

Given the temperatures T_{sf}^m , T_s^m , and T_{ik}^m at time m , we solve a set of finite-difference equations to obtain the new temperatures at time $m + 1$. Each temperature is coupled to the temperatures of the layers immediately above and below by heat conduction terms that are treated implicitly. For example, the rate of change of T_{ik} depends on the new temperatures in layers $k - 1$, k , and $k + 1$. Thus we have a set of equations of the form

$$\mathbf{A}\mathbf{x} = \mathbf{b}, \quad (2.93)$$

where \mathbf{A} is a tridiagonal matrix, \mathbf{x} is a column vector whose components are the unknown new temperatures, and \mathbf{b} is another column vector. Given \mathbf{A} and \mathbf{b} , we can compute \mathbf{x} with a standard tridiagonal solver.

There are four general cases: (1) $T_{sf} < 0^\circ\text{C}$, snow present; (2) $T_{sf} = 0^\circ\text{C}$, snow present; (3) $T_{sf} < 0^\circ\text{C}$, snow absent; and (4) $T_{sf} = 0^\circ\text{C}$, snow absent. For case 1 we have one equation (the top row of the matrix) for the new surface temperature, N_s equations for the new snow temperatures, and N_i equations for the new ice temperatures. For cases 2 and 4 we omit the equation for the surface temperature, which is held at 0°C , and for cases 3 and 4 we omit the snow temperature equations. Snow is considered absent if the snow depth is less than a user-specified minimum value, `hs_min`. (Very thin snow layers are still transported conservatively by the transport modules; they are simply ignored by the thermodynamics.)

The rate of temperature change in the ice interior is given by [38]:

$$\rho_i c_i \frac{\partial T_i}{\partial t} = \frac{\partial}{\partial z} \left(K_i \frac{\partial T_i}{\partial z} \right) - \frac{\partial}{\partial z} [I_{pen}(z)], \quad (2.94)$$

where $\rho_i = 917 \text{ kg/m}^3$ is the sea ice density (assumed to be uniform), $c_i(T, S)$ is the specific heat of sea ice, $K_i(T, S)$ is the thermal conductivity of sea ice, I_{pen} is the flux of penetrating solar radiation at depth z , and z is the vertical coordinate, defined to be positive downward with $z = 0$ at the top surface. If `shortwave = 'ccsm3'`, the penetrating radiation is given by Beer's Law:

$$I_{pen}(z) = I_0 \exp(-\kappa_i z),$$

where I_0 is the penetrating solar flux at the top ice surface and κ_i is an extinction coefficient. If `shortwave = 'dEdd'`, then solar absorption is computed by the Delta-Eddington scheme.

The specific heat of sea ice is given to an excellent approximation by [40]

$$c_i(T, S) = c_0 + \frac{L_0 \mu S}{T^2}, \quad (2.95)$$

where $c_0 = 2106 \text{ J/kg/deg}$ is the specific heat of fresh ice at , $L_0 = 3.34 \times 10^5 \text{ J/kg}$ is the latent heat of fusion of fresh ice at , and $\mu = 0.054 \text{ deg/ppt}$ is the (liquidus) ratio between the freezing temperature and salinity of brine.

Following [54] and [38], the standard thermal conductivity (`conduct = 'MU71'`) is given by

$$K_i(T, S) = K_0 + \frac{\beta S}{T}, \quad (2.96)$$

where $K_0 = 2.03 \text{ W/m/deg}$ is the conductivity of fresh ice and $\beta = 0.13 \text{ W/m/ppt}$ is an empirical constant. Experimental results [51] suggest that Equation (2.96) may not be a good description of the thermal conductivity of sea ice. In particular, the measured conductivity does not markedly decrease as T approaches 0°C , but does decrease near the top surface (regardless of temperature).

An alternative parameterization based on the “bubbly brine” model of [41] for conductivity is available (`conduct = 'bubbly'`):

$$K_i = \frac{\rho_i}{\rho_0} (2.11 - 0.011T + 0.09S/T), \quad (2.97)$$

where ρ_i and $\rho_0 = 917 \text{ kg/m}^3$ are densities of sea ice and pure ice. Whereas the parameterization in Equation (2.96) asymptotes to a constant conductivity of $2.03 \text{ W m}^{-1} \text{ K}^{-1}$ with decreasing T , K_i in Equation (2.97) continues to increase with colder temperatures.

The equation for temperature changes in snow is analogous to Equation (2.94), with $\rho_s = 330 \text{ kg/m}^3$, $c_s = c_0$, and $K_s = 0.30 \text{ W/m/deg}$ replacing the corresponding ice values. If shortwave = ‘ccsm3’, then the penetrating solar radiation is equal to zero for snow-covered ice, since most of the incoming sunlight is absorbed near the top surface. If shortwave = ‘dEdd’, however, then I_{pen} is nonzero in snow layers.

It is possible that more shortwave penetrates into an ice layer than is needed to completely melt the layer, or else it causes the computed temperature to be greater than the melting temperature, which until now has caused the vertical thermodynamics code to abort. A parameter `frac` = 0.9 sets the fraction of the ice layer than can be melted through. A minimum temperature difference for absorption of radiation is also set, currently `dTemp` = 0.02 (K). The limiting occurs in **icepack_therm_vertical.F90**, for both the ccs3 and delta Eddington radiation schemes. If the available energy would melt through a layer, then penetrating shortwave is first reduced, possibly to zero, and if that is insufficient then the local conductivity is also reduced to bring the layer temperature just to the melting point.

We now convert Equation (2.94) to finite-difference form. The resulting equations are second-order accurate in space, except possibly at material boundaries, and first-order accurate in time. Before writing the equations in full we give finite-difference expressions for some of the terms.

First consider the terms on the left-hand side of Equation (2.94). We write the time derivatives as

$$\frac{\partial T}{\partial t} = \frac{T^{m+1} - T^m}{\Delta t},$$

where T is the temperature of either ice or snow and m is a time index. The specific heat of ice layer k is approximated as

$$c_{ik} = c_0 + \frac{L_0 \mu S_{ik}}{T_{ik}^m T_{ik}^{m+1}}, \quad (2.98)$$

which ensures that energy is conserved during a change in temperature. This can be shown by using Equation (2.95) to integrate $c_i dT$ from T_{ik}^m to T_{ik}^{m+1} ; the result is $c_{ik}(T_{ik}^{m+1} - T_{ik}^m)$, where c_{ik} is given by Equation (2.98). The specific heat is a nonlinear function of T_{ik}^{m+1} , the unknown new temperature. We can retain a set of linear equations, however, by initially guessing $T_{ik}^{m+1} = T_{ik}^m$ and then iterating the solution, updating T_{ik}^{m+1} in Equation (2.98) with each iteration until the solution converges.

Next consider the first term on the right-hand side of Equation (2.94). The first term describes heat diffusion and is discretized for a given ice or snow layer k as

$$\frac{\partial}{\partial z} \left(K \frac{\partial T}{\partial z} \right) = \frac{1}{\Delta h} [K_k^*(T_{k-1}^{m+1} - T_k^{m+1}) - K_{k+1}^*(T_k^{m+1} - T_{k+1}^{m+1})], \quad (2.99)$$

where Δh is the layer thickness and K_k is the effective conductivity at the upper boundary of layer k . This discretization is centered and second-order accurate in space, except at the boundaries. The flux terms on the right-hand side (RHS) are treated implicitly; i.e., they depend on the temperatures at the new time $m + 1$. The resulting scheme is first-order accurate in time and unconditionally stable. The effective conductivity K^* at the interface of layers $k - 1$ and k is defined as

$$K_k^* = \frac{2K_{k-1}K_k}{K_{k-1}h_k + K_k h_{k-1}},$$

which reduces to the appropriate values in the limits $K_k \gg K_{k-1}$ (or vice versa) and $h_k \gg h_{k-1}$ (or vice versa). The effective conductivity at the top (bottom) interface of the ice-snow column is given by $K^* = 2K/\Delta h$, where K and Δh are the thermal conductivity and thickness of the top (bottom) layer. The second term on the RHS of Equation (2.94) is discretized as

$$\frac{\partial}{\partial z} [I_{pen}(z)] = I_0 \frac{\tau_{k-1} - \tau_k}{\Delta h} = \frac{I_k}{\Delta h}$$

where τ_k is the fraction of the penetrating solar radiation I_0 that is transmitted through layer k without being absorbed. We now construct a system of equations for the new temperatures. For $T_{sf} < 0^\circ\text{C}$ we require

$$F_0 = F_{ct}, \quad (2.100)$$

where F_{ct} is the conductive flux from the top surface to the ice interior, and both fluxes are evaluated at time $m + 1$. Although F_0 is a nonlinear function of T_{sf} , we can make the linear approximation

$$F_0^{m+1} = F_0^* + \left(\frac{dF_0}{dT_{sf}} \right)^* (T_{sf}^{m+1} - T_{sf}^*),$$

where T_{sf}^* is the surface temperature from the most recent iteration, and F_0^* and $(dF_0/dT_{sf})^*$ are functions of T_{sf}^* . We initialize $T_{sf}^* = T_{sf}^m$ and update it with each iteration. Thus we can rewrite Equation (2.100) as

$$F_0^* + \left(\frac{dF_0}{dT_{sf}} \right)^* (T_{sf}^{m+1} - T_{sf}^*) = K_1^* (T_{sf}^{m+1} - T_1^{m+1}),$$

Rearranging terms, we obtain

$$\left[\left(\frac{dF_0}{dT_{sf}} \right)^* - K_1^* \right] T_{sf}^{m+1} + K_1^* T_1^{m+1} = \left(\frac{dF_0}{dT_{sf}} \right)^* T_{sf}^* - F_0^*, \quad (2.101)$$

the first equation in the set of equations (2.93). The temperature change in ice/snow layer k is

$$\rho_k c_k \frac{(T_k^{m+1} - T_k^m)}{\Delta t} = \frac{1}{\Delta h_k} [K_k^* (T_{k-1}^{m+1} - T_k^{m+1}) - K_{k+1} (T_k^{m+1} - T_{k+1}^{m+1})], \quad (2.102)$$

where $T_0 = T_{sf}$ in the equation for layer 1. In tridiagonal matrix form, Equation (2.102) becomes

$$-\eta_k K_k T_{k-1}^{m+1} + [1 + \eta_k (K_k + K_{k+1})] T_k^{m+1} - \eta_k K_{k+1} T_{k+1}^{m+1} = T_k^m + \eta_k I_k, \quad (2.103)$$

where $\eta_k = \Delta t / (\rho_k c_k \Delta h_k)$. In the equation for the bottom ice layer, the temperature at the ice–ocean interface is held fixed at T_f , the freezing temperature of the mixed layer; thus the last term on the LHS is known and is moved to the RHS. If $T_{sf} = 0^\circ\text{C}$, then there is no surface flux equation. In this case the first equation in Equation (2.93) is similar to Equation (2.103), but with the first term on the LHS moved to the RHS.

These equations are modified if T_{sf} and F_{ct} are computed within the atmospheric model and passed to the host sea ice model (`calc_Tsfc` = false; see [Atmosphere](#)). In this case there is no surface flux equation. The top layer temperature is computed by an equation similar to Equation (2.103) but with the first term on the LHS replaced by $\eta_1 F_{ct}$ and moved to the RHS. The main drawback of treating the surface temperature and fluxes explicitly is that the solution scheme is no longer unconditionally stable. Instead, the effective conductivity in the top layer must satisfy a diffusive CFL condition:

$$K^* \leq \frac{\rho c h}{\Delta t}.$$

For thin layers and typical coupling intervals (~ 1 hr), K^* may need to be limited before being passed to the atmosphere via the coupler. Otherwise, the fluxes that are returned to the host sea ice model may result in oscillating, highly inaccurate temperatures. The effect of limiting is to treat the ice as a poor heat conductor. As a result, winter growth rates are reduced, and the ice is likely to be too thin (other things being equal). The values of `hs_min` and Δt must therefore be chosen with care. If `hs_min` is too small, frequent limiting is required, but if `hs_min` is too large, snow will be ignored when its thermodynamic effects are significant. Likewise, infrequent coupling requires more limiting, whereas frequent coupling is computationally expensive.

This completes the specification of the matrix equations for the four cases. We compute the new temperatures using a tridiagonal solver. After each iteration we check to see whether the following conditions hold:

1. $T_{sf} \leq 0^\circ\text{C}$.

2. The change in T_{sf} since the previous iteration is less than a prescribed limit, ΔT_{\max} .
3. $F_0 \geq F_{ct}$. (If $F_0 < F_{ct}$, ice would be growing at the top surface, which is not allowed.)
4. The rate at which energy is added to the ice by the external fluxes equals the rate at which the internal ice energy is changing, to within a prescribed limit ΔF_{\max} .

We also check the convergence rate of T_{sf} . If T_{sf} is oscillating and failing to converge, we average temperatures from successive iterations to improve convergence. When all these conditions are satisfied—usually within two to four iterations for $\Delta T_{\max} \approx 0.01^\circ\text{C}$ and $\Delta F_{\max} \approx 0.01 \text{ W/m}^2$ —the calculation is complete.

To compute growth and melt rates (*Growth and melting*), we derive expressions for the enthalpy q . The enthalpy of snow (or fresh ice) is given by

$$q_s(T) = -\rho_s(-c_0T + L_0).$$

Sea ice enthalpy is more complex, because of brine pockets whose salinity varies inversely with temperature. Since the salinity is prescribed, there is a one-to-one relationship between temperature and enthalpy. The specific heat of sea ice, given by Equation (2.95), includes not only the energy needed to warm or cool ice, but also the energy used to freeze or melt ice adjacent to brine pockets. Equation (2.95) can be integrated to give the energy δ_e required to raise the temperature of a unit mass of sea ice of salinity S from T to T' :

$$\delta_e(T, T') = c_0(T' - T) + L_0\mu S \left(\frac{1}{T} - \frac{1}{T'} \right).$$

If we let $T' = T_m \equiv -\mu S$, the temperature at which the ice is completely melted, we have

$$\delta_e(T, T_m) = c_0(T_m - T) + L_0 \left(1 - \frac{T_m}{T} \right).$$

Multiplying by ρ_i to change the units from J/kg to J/m³ and adding a term for the energy needed to raise the meltwater temperature to , we obtain the sea ice enthalpy:

$$q_i(T, S) = -\rho_i \left[c_0(T_m - T) + L_0 \left(1 - \frac{T_m}{T} \right) - c_w T_m \right] \quad (2.104)$$

Note that Equation (2.104) is a quadratic equation in T . Given the layer enthalpies we can compute the temperatures using the quadratic formula:

$$T = \frac{-b - \sqrt{b^2 - 4ac}}{2a},$$

where

$$\begin{aligned} a &= c_0, \\ b &= (c_w - c_0) T_m - \frac{q_i}{\rho_i} - L_0, \\ c &= L_0 T_m. \end{aligned}$$

The other root is unphysical.

Mushy thermodynamics (ktherm = 2)

The “mushy” thermodynamics option treats the sea ice as a mushy layer [11] in which the ice is assumed to be composed of microscopic brine inclusions surrounded by a matrix of pure water ice. Both enthalpy and salinity are prognostic variables. The size of the brine inclusions is assumed to be much smaller than the size of the ice layers, allowing a continuum approximation: a bulk sea-ice quantity is taken to be the liquid-fraction-weighted average of that quantity in the ice and in the brine.

Enthalpy and mushy physics

The mush enthalpy, q , is related to the temperature, T , and the brine volume, ϕ , by

$$q = \phi q_{br} + (1 - \phi) q_i = \phi \rho_w c_w T + (1 - \phi) (\rho_i c_i T - \rho_i L_0) \quad (2.105)$$

where q_{br} is the brine enthalpy, q_i is the pure ice enthalpy, ρ_i and c_i are density and heat capacity of the ice, ρ_w and c_w are density and heat capacity of the brine and L_0 is the latent heat of melting of pure ice. We assume that the specific heats of the ice and brine are fixed at the values of `cp_ice` and `cp_ocn`, respectively. The enthalpy is the energy required to raise the temperature of the sea ice to 0°C , including both sensible and latent heat changes. Since the sea ice contains salt, it usually will be fully melted at a temperature below 0°C . Equations (2.104) and (2.105) are equivalent except for the density used in the term representing the energy required to bring the melt water temperature to (ρ_i and ρ_w in equations (2.104) and (2.105), respectively).

The liquid fraction, ϕ , of sea ice is given by

$$\phi = \frac{S}{S_{br}}$$

where the brine salinity, S_{br} , is given by the liquidus relation using the ice temperature.

Within the parameterizations of brine drainage the brine density is a function of brine salinity [39]:

$$\rho(S_{br}) = 1000.3 + 0.78237 S_{br} + 2.8008 \times 10^{-4} S_{br}^2.$$

Outside the parameterizations of brine drainage the densities of brine and ice are fixed at the values of ρ_w and ρ_i , respectively.

The permeability of ice is computed from the liquid fraction as in [18]:

$$\Pi(\phi) = 3 \times 10^{-8} (\phi - \phi_\Pi)^3$$

where ϕ_Π is 0.05.

The liquidus relation used in the mushy layer module is based on observations of [4]. A piecewise linear relation can be fitted to observations of Z (the ratio of mass of salt (in g) to mass of pure water (in kg) in brine) to the melting temperature: $Z = aT + b$. Salinity is the mass of salt (in g) per mass of brine (in kg) so is related to Z by

$$\frac{1}{S} = \frac{1}{1000} + \frac{1}{Z}.$$

The data is well fitted with two linear regions,

$$S_{br} = \frac{(T + J_1)}{(T/1000 + L_1)} l_0 + \frac{(T + J_2)}{(T/1000 + L_2)} (1 - l_0)$$

where

$$l_0 = \begin{cases} 1 & \text{if } T \geq T_0 \\ 0 & \text{if } T < T_0 \end{cases},$$

$$J_{1,2} = \frac{b_{1,2}}{a_{1,2}},$$

$$L_{1,2} = \frac{(1 + b_{1,2}/1000)}{a_{1,2}}.$$

T_0 is the temperature at which the two linear regions meet. Fitting to the data, $T_0 = -7.636^\circ\text{C}$, $a_1 = -18.48 \text{ g kg}^{-1} \text{ K}^{-1}$, $a_2 = -10.3085 \text{ g kg}^{-1} \text{ K}^{-1}$, $b_1 = 0$ and $b_2 = 62.4 \text{ g kg}^{-1}$.

Two-stage outer iteration

As for the BL99 thermodynamics [6] there are two qualitatively different situations that must be considered when solving for the vertical thermodynamics: the surface can be melting and at the melting temperature, or the surface can be colder than the melting temperature and not melting. In the BL99 thermodynamics these two situations were treated within the same iterative loop, but here they are dealt with separately. If at the beginning of the time step the ice surface is cold and not melting, we solve the ice temperatures assuming that this is also true at the end of the time step. Once we have solved for the new temperatures we test to see if the answer is consistent with this assumption. If the surface temperature is below the melting temperature then we have found the appropriate consistent solution. If the surface is above the melting temperature at the end of the initial solution attempt, we recalculate the new temperatures assuming the surface temperature is fixed at the melting temperature. Alternatively if the surface is at the melting temperature at the start of a time step, we assume initially that this is also the case at the end of the time step, solve for the new temperatures and then check that the surface conductive heat flux is less than the surface atmospheric heat flux as is required for a melting surface. If this is not the case, the temperatures are recalculated assuming the surface is colder than melting. We have found that solutions of the temperature equations that only treat one of the two qualitatively different solutions at a time are more numerically robust than if both are solved together. The surface state rarely changes qualitatively during the solution so the method is also numerically efficient.

Temperature updates

During the calculation of the new temperatures and salinities, the liquid fraction is held fixed at the value from the previous time step. Updating the liquid fraction during the Picard iteration described below was found to be numerically unstable. Keeping the liquid fraction fixed drastically improves the numerical stability of the method without significantly changing the solution.

Temperatures are calculated in a similar way to BL99 with an outer Picard iteration of an inner tridiagonal matrix solve. The conservation equation for the internal ice temperatures is

$$\frac{\partial q}{\partial t} = \frac{\partial}{\partial z} \left(K \frac{\partial T}{\partial z} \right) + w \frac{\partial q_{br}}{\partial z} + F$$

where q is the sea ice enthalpy, K is the bulk thermal conductivity of the ice, w is the vertical Darcy velocity of the brine, q_{br} is the brine enthalpy and F is the internally absorbed shortwave radiation. The first term on the right represents heat conduction and the second term represents the vertical advection of heat by gravity drainage and flushing.

The conductivity of the mush is given by

$$K = \phi K_{br} + (1 - \phi) K_i$$

where $K_i = 2.3 \text{ W m}^{-1} \text{ K}^{-1}$ is the conductivity of pure ice and $K_{br} = 0.5375 \text{ W m}^{-1} \text{ K}^{-1}$ is the conductivity of the brine. The thermal conductivity of brine is a function of temperature and salinity, but here we take it as a constant value for the middle of the temperature range experienced by sea ice, -10°C [47], assuming the brine liquidus salinity at -10°C .

We discretize the terms that include temperature in the heat conservation equation as

$$\frac{q_k^t - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'} (T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'} (T_k^t - T_{k-1}^t)}{\Delta h} \quad (2.106)$$

where the superscript signifies whether the quantity is evaluated at the start (t_0) or the end (t) of the time step and the subscript indicates the vertical layer. Writing out the temperature dependence of the enthalpy term we have

$$\frac{(\phi(c_w \rho_w - c_i \rho_i) + c_i \rho_i) T_k^t - (1 - \phi) \rho_i L - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'} (T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'} (T_k^t - T_{k-1}^t)}{\Delta h}.$$

The mush thermal conductivities are fixed at the start of the timestep. For the lowest ice layer T_{k+1} is replaced with T_{bot} , the temperature of the ice base. Δh is the layer thickness and z_k' is the distance between the $k-1$ and k layer centers.

Similarly, for the snow layer temperatures we have the following discretized equation:

$$\frac{c_i \rho_s T_k^t - \rho_s L_0 - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'} (T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'} (T_k^t - T_{k-1}^t)}{\Delta h}.$$

For the upper-most layer (either ice layer or snow layer if it present) T_{k-1} is replaced with T_{sf} , the temperature of the surface.

If the surface is colder than the melting temperature then we also have to solve for the surface temperature, T_{sf} . Here we follow the methodology of BL99 described above.

These discretized temperature equations form a tridiagonal matrix for the new temperatures and are solved with a standard tridiagonal solver. A Picard iteration is used to incorporate nonlinearity in the equations. The surface heat flux is a function of surface temperature and with each iteration, the surface heat flux is calculated with the new surface temperature until convergence is achieved. Convergence normally occurs after a few iterations once the temperature changes during an iteration fall below 5×10^{-4} °C and the energy conservation error falls below 0.9 *fermax*.

Salinity updates

Several physical processes alter the sea ice bulk salinity. New ice forms with the salinity of the sea water from which it formed. Gravity drainage reduces the bulk salinity of newly formed sea ice, while flushing of melt water through the ice also alters the salinity profile.

The salinity equation takes the form

$$\frac{\partial S}{\partial t} = w \frac{\partial S_{br}}{\partial z} + G$$

where w is a vertical Darcy velocity and G is a source term. The right-hand side depends indirectly on the bulk salinity through the liquid fraction ($S = \phi S_{br}$). Since ϕ is fixed for the time step, we solve the salinity equation explicitly after the temperature equation is solved.

A. Gravity drainage. Sea ice initially retains all the salt present in the sea water from which it formed. Cold temperatures near the top surface of forming sea ice result in higher brine salinities there, because the brine is always at its melting temperature. This colder, saltier brine is denser than the underlying sea water and the brine undergoes convective overturning with the ocean. As the dense, cold brine drains out of the ice, it is replaced by fresher seawater, lowering the bulk salinity of the ice. Following [53], gravity drainage is assumed to occur as two simultaneously operating modes: a rapid mode operating principally near the ice base and a slow mode occurring everywhere.

Rapid drainage takes the form of a vertically varying upward Darcy flow. The contribution to the bulk salinity equation for the rapid mode is

$$\left. \frac{\partial S}{\partial t} \right|_{\text{rapid}} = w(z) \frac{\partial S_{br}}{\partial z}$$

where S is the bulk salinity and S_{br} is the brine salinity, specified by the liquidus relation with ice temperature. This equation is discretized using an upwind advection scheme,

$$\frac{S_k^t - S_k^{t_0}}{\Delta t} = w_k \frac{S_{br k+1} - S_{br k}}{\Delta z}.$$

The upward advective flow also carries heat, contributing a term to the heat conservation Equation (2.106),

$$\left. \frac{\partial q}{\partial t} \right|_{\text{rapid}} = w(z) \frac{\partial q_{br}}{\partial z}$$

where q_{br} is the brine enthalpy. This term is discretized as

$$\left. \frac{q_k^t - q_k^{t_0}}{\Delta t} \right|_{\text{rapid}} = w_k \frac{q_{br k+1} - q_{br k}}{\Delta z}.$$

$$w_k = \max_{j=k,n} (\tilde{w}_j)$$

where the maximum is taken over all the ice layers between layer k and the ice base. \tilde{w}_j is given by

$$\tilde{w}(z) = w \left(\frac{Ra(z) - Ra_c}{Ra(z)} \right). \quad (2.107)$$

where Ra_c is a critical Rayleigh number and $Ra(z)$ is the local Rayleigh number at a particular level,

$$Ra(z) = \frac{g\Delta\rho\Pi(h-z)}{\kappa\eta}$$

where $\Delta\rho$ is the difference in density between the brine at z and the ocean, Π is the minimum permeability between z and the ocean, h is the ice thickness, κ is the brine thermal diffusivity and η is the brine dynamic viscosity. Equation (2.107) reduces the flow rate for Rayleigh numbers below the critical Rayleigh number.

The unmodified flow rate, w , is determined from a hydraulic pressure balance argument for upward flow through the mush and returning downward flow through ice free channels:

$$w(z)\Delta x^2 = A_m \left(-\frac{\Delta P}{l} + B_m \right)$$

where

$$\begin{aligned} \frac{\Delta P}{l} &= \frac{A_p B_p + A_m B_m}{A_m + A_p}, \\ A_m &= \frac{\Delta x^2}{\eta} \frac{n}{\sum_{k=1}^n \frac{1}{\Pi(k)}}, \\ B_m &= -\frac{g}{n} \sum_{k=1}^n \rho(k), \\ A_p &= \frac{\pi a^4}{8\eta}, \\ B_p &= -\rho_p g. \end{aligned}$$

There are three tunable parameters in the above parameterization, a , the diameter of the channel, Δx , the horizontal size of the mush draining through each channel, and Ra_c , the critical Rayleigh number. ρ_p is the density of brine in the channel which we take to be the density of brine in the mush at the level that the brine is draining from. l is the thickness of mush from the ice base to the top of the layer in question. We assume that Δx is proportional to l so that $\Delta x = 2\beta l$. a (`a_rapid_mode`), β (`aspect_rapid_mode`) and Ra_c (`Ra_c_rapid_mode`) are all namelist parameters with default values of 0.5 mm, 1 and 10, respectively. The value $\beta = 1$ gives a square aspect ratio for the convective flow in the mush.

The *slow drainage* mode takes the form of a simple relaxation of bulk salinity:

$$\left. \frac{\partial S(z)}{\partial t} \right|_{slow} = -\lambda(S(z) - S_c).$$

The decay constant, λ , is modeled as

$$\lambda = S^* \max \left(\frac{T_{bot} - T_{sf}}{h}, 0 \right)$$

where S^* is a tuning parameter for the drainage strength, T_{bot} is the basal ice temperature, T_{sf} is the upper surface temperature and h is the ice thickness. The bulk salinity relaxes to a value, $S_c(z)$, given by

$$S_c(z) = \phi_c S_{br}(z)$$

where $S_{br}(z)$ is the brine salinity at depth z and ϕ_c is a critical liquid fraction. Both S^* and ϕ_c are namelist parameters, $dSdt_slow_mode = 1.5 \times 10^{-7} \text{ m s}^{-1} \text{ K}^{-1}$ and $\phi_{c_slow_mode} = 0.05$.

B. Downwards flushing. Melt pond water drains through sea ice and flushes out brine, reducing the bulk salinity of the sea ice. This is modeled with the mushy physics option as a vertical Darcy flow through the ice that affects both the enthalpy and bulk salinity of the sea ice:

$$\left. \frac{\partial q}{\partial t} \right|_{flush} = w_f \frac{\partial q_{br}}{\partial z}$$

$$\left. \frac{\partial S}{\partial t} \right|_{flush} = w_f \frac{\partial S_{br}}{\partial z}$$

These equations are discretized with an upwind advection scheme. The flushing Darcy flow, w_f , is given by

$$w_f = \frac{\bar{\Pi} \rho_w g \Delta h}{h \eta},$$

where $\bar{\Pi}$ is the harmonic mean of the ice layer permeabilities and Δh is the hydraulic head driving melt water through the sea ice. It is the difference in height between the top of the melt pond and sea level.

Basal boundary condition

In traditional Stefan problems the ice growth rate is calculated by determining the difference in heat flux on either side of the ice/ocean interface and equating this energy difference to the latent heat of new ice formed. Thus,

$$(1 - \phi_i) L_0 \rho_i \frac{\partial h}{\partial t} = K \left. \frac{\partial T}{\partial z} \right|_i - K_w \left. \frac{\partial T}{\partial z} \right|_w \quad (2.108)$$

where $(1 - \phi_i)$ is the solid fraction of new ice formed and the right hand is the difference in heat flux at the ice–ocean interface between the ice side and the ocean side of the interface. However, with mushy layers there is usually no discontinuity in solid fraction across the interface, so $\phi_i = 1$ and Equation (2.108) cannot be used explicitly. To circumvent this problem we set the interface solid fraction to be 0.15, a value that reproduces observations. ϕ_i is a namelist parameter ($\phi_{i_mushy} = 0.85$). The basal ice temperature is set to the liquidus temperature T_f of the ocean surface salinity.

Tracer consistency

In order to ensure conservation of energy and salt content, the advection routines will occasionally limit changes to either enthalpy or bulk salinity. The mushy thermodynamics routine determines temperature from both enthalpy and bulk salinity. Since the limiting changes performed in the advection routine are not applied consistently (from a mushy physics point of view) to both enthalpy and bulk salinity, the resulting temperature may be changed to be greater than the limit allowed in the thermodynamics routines. If this situation is detected, the code corrects the enthalpy so the temperature is below the limiting value. Conservation of energy is ensured by placing the excess energy in the ocean, and the code writes a warning (see *The Warning Package*) that this has occurred to the diagnostics file. This situation only occurs with the mushy thermodynamics, and it should only occur very infrequently and have a minimal effect on results. The addition of the heat to the ocean may reduce ice formation by a small amount afterwards.

2.6.4 Growth and melting

Melting at the top surface is given by

$$q \delta h = \begin{cases} (F_0 - F_{ct}) \Delta t & \text{if } F_0 > F_{ct} \\ 0 & \text{otherwise} \end{cases} \quad (2.109)$$

where q is the enthalpy of the surface ice or snow layer¹ (recall that $q < 0$) and δh is the change in thickness. If the layer melts completely, the remaining flux is used to melt the layers beneath. Any energy left over when the ice and

¹ The mushy thermodynamics option does not include the enthalpy associated with raising the meltwater temperature to in these calculations, unlike BL99, which does include it. This extra heat is returned to the ocean (or the atmosphere, in the case of evaporation) with the melt water.

snow are gone is added to the ocean mixed layer. Ice cannot grow at the top surface due to conductive fluxes; however, snow–ice can form. New snowfall is added at the end of the thermodynamic time step.

Growth and melting at the bottom ice surface are governed by

$$q \delta h = (F_{cb} - F_{bot}) \Delta t, \quad (2.110)$$

where F_{bot} is given by Equation (2.91) and F_{cb} is the conductive heat flux at the bottom surface:

$$F_{cb} = \frac{K_{i,N+1}}{\Delta h_i} (T_{iN} - T_f).$$

If ice is melting at the bottom surface, q in Equation (2.110) is the enthalpy of the bottom ice layer. If ice is growing, q is the enthalpy of new ice with temperature T_f and salinity S_{max} (`kt herm` = 1) or ocean surface salinity (`kt herm` = 2). This ice is added to the bottom layer.

In general, frazil ice formed in the ocean is added to the thinnest ice category. The new ice is grown in the open water area of the grid cell to a specified minimum thickness; if the open water area is nearly zero or if there is more new ice than will fit into the thinnest ice category, then the new ice is spread over the entire cell.

If the latent heat flux is negative (i.e., latent heat is transferred from the ice to the atmosphere), snow or snow-free ice sublimates at the top surface. If the latent heat flux is positive, vapor from the atmosphere is deposited at the surface as snow or ice. The thickness change of the surface layer is given by

$$(\rho L_v - q) \delta h = F_l \Delta t, \quad (2.111)$$

where ρ is the density of the surface material (snow or ice), and $L_v = 2.501 \times 10^6$ J/kg is the latent heat of vaporization of liquid water at 0°C . Note that ρL_v is nearly an order of magnitude larger than typical values of q . For positive latent heat fluxes, the deposited snow or ice is assumed to have the same enthalpy as the existing surface layer.

After growth and melting, the various ice layers no longer have equal thicknesses. We therefore adjust the layer interfaces, conserving energy, so as to restore layers of equal thickness $\Delta h_i = h_i/N_i$. This is done by computing the overlap η_{km} of each new layer k with each old layer m :

$$\eta_{km} = \min(z_m, z_k) - \max(z_{m-1}, z_{k-1}),$$

where z_m and z_k are the vertical coordinates of the old and new layers, respectively. The enthalpies of the new layers are

$$q_k = \frac{1}{\Delta h_i} \sum_{m=1}^{N_i} \eta_{km} q_m.$$

Lateral melting is accomplished by multiplying the state variables by $1 - r_{side}$, where r_{side} is the fraction of ice melted laterally [37][48], and adjusting the ice energy and fluxes as appropriate. We assume a floe diameter of 300 m.

2.6.5 Snow-ice formation

At the end of the time step we check whether the snow is deep enough to lie partially below the surface of the ocean (freeboard). From Archimedes' principle, the base of the snow is at sea level when

$$\rho_i h_i + \rho_s h_s = \rho_w h_i.$$

Thus the snow base lies below sea level when

$$h^* \equiv h_s - \frac{(\rho_w - \rho_i) h_i}{\rho_s} > 0.$$

In this case, for $k_{\text{therm}} = 1$ (BL99) we raise the snow base to sea level by converting some snow to ice:

$$\begin{aligned}\delta h_s &= \frac{-\rho_i h^*}{\rho_w}, \\ \delta h_i &= \frac{\rho_s h^*}{\rho_w}.\end{aligned}$$

In rare cases this process can increase the ice thickness substantially. For this reason snow–ice conversions are postponed until after the remapping in thickness space (*Transport in thickness space*), which assumes that ice growth during a single time step is fairly small.

For $k_{\text{therm}} = 2$ (mushy), we model the snow–ice formation process as follows: If the ice surface is below sea level then we replace some snow with the same thickness of sea ice. The thickness change chosen is that which brings the ice surface to sea level. The new ice has a porosity of the snow, which is calculated as

$$\phi = 1 - \frac{\rho_s}{\rho_i}$$

where ρ_s is the density of snow and ρ_i is the density of fresh ice. The salinity of the brine occupying the above porosity within the new ice is taken as the sea surface salinity. Once the new ice is formed, the vertical ice and snow layers are regridded into equal thicknesses while conserving energy and salt.

2.7 Biogeochemistry

2.7.1 Aerosols

Basic Aerosols

Aerosols may be deposited on the ice and gradually work their way through it until the ice melts and they are passed into the ocean. They are defined as ice and snow volume tracers (Eq. 15 and 16 in CICE.v5 documentation), with the snow and ice each having two tracers for each aerosol species, one in the surface scattering layer (delta-Eddington SSL) and one in the snow or ice interior below the SSL.

Rather than updating aerosols for each change to ice/snow thickness due to evaporation, melting, snow-ice formation, etc., during the thermodynamics calculation, these changes are deduced from the diagnostic variables (melts, meltb, snoice, etc) in **icepack_aerosol.F90**. Three processes change the volume of ice or snow but do not change the total amount of aerosol, thus causing the aerosol concentration (the value of the tracer itself) to increase: evaporation, snow deposition and basal ice growth. Basal and lateral melting remove all aerosols in the melted portion. Surface ice and snow melt leave a significant fraction of the aerosols behind, but they do “scavenge” a fraction of them given by the parameter $k_{\text{scav}} = [0.03, 0.2, 0.02, 0.02, 0.01, 0.01]$ (only the first 3 are used in CESM, for their 3 aerosol species). Scavenging also applies to snow-ice formation. When sea ice ridges, a fraction of the snow on the ridging ice is thrown into the ocean, and any aerosols in that fraction are also lost to the ocean.

As upper SSL or interior layers disappear from the snow or ice, aerosols are transferred to the next lower layer, or into the ocean when no ice remains. The atmospheric flux faero_atm contains the rates of aerosol deposition for each species, while faero_ocn has the rate at which the aerosols are transferred to the ocean.

The aerosol tracer flag tr_aero must be set to true in **icepack_in**, and the number of aerosol species is set in **icepack.settings**; CESM uses 3.

Z-Aerosols

An alternate scheme for aerosols in sea ice is available using the brine motion based transport scheme of the biogeochemical tracers. All vertically resolved biogeochemical tracers (z-tracers), including aerosols, have the potential to be atmospherically deposited onto the snow or ice, scavenged during snow melt, and passed into the brine. The mobile

fraction (discussed in *Mobile and stationary phases*) is then transported via brine drainage processes (Eq. (2.128)) while a stationary fraction (discussed in *Mobile and stationary phases*) adheres to the ice crystals. Snow deposition and the process of scavenging aerosols during snow melt is consistent with the basic aerosol scheme, though parameters have been generalized to accomodate potential atmospheric deposition for all z-tracers. For an example, see the scavenging parameter `kscavz` for z-tracers defined in **icepack_zbgc_shared.F90**.

Within the snow, z-tracers are defined as concentrations in the snow surface layer (h_{ssl}) and the snow interior ($h_s - h_{ssl}$). The total snow content of z-tracers per ice area per grid cell area, C_{snow} is

$$C_{snow} = C_{ssl}h_{ssl} + C_{sint}(h_s - h_{ssl})$$

One major difference in how the two schemes model snow aerosol transport is that the fraction scavenged from snow melt in the z-tracer scheme is not immediately fluxed into the ocean, but rather, enters the ice as a source of low salinity but potentially tracer-rich brine. The snow melt source is included as a surface flux condition in **icepack_algae.F90**.

All the z-aerosols are nonreactive with the exception of the dust aerosols. We assume that a small fraction of the dust flux into the ice has soluble iron (`dustFe_sol` in **icepack_in**) and so is passed to the dissolved iron tracer. The remaining dust passes through the ice without reactions.

To use z-aerosols, `tr_zaero` must be set to true in **icepack_in**, and the number of z-aerosol species is set in **icepack.settings**, `TRZAERO`. Note, the basic tracers `tr_aero` must be false and `NTRAERO` in **icepack.settings** should be 0. In addition, z-tracers and the brine height tracer must also be active. These are set in **icepack_in** with `tr_brine` and `z_tracer` set to true. In addition, to turn on the radiative coupling between the aerosols and the Delta-Eddington radiative scheme, `shortwave` must equal 'dEdd' and `dEdd_algae` must be true in **icepack_in**.

2.7.2 Brine height

The brine height, h_b , is the distance from the ice-ocean interface to the brine surface. When `tr_brine` is set true in **icepack_in** and `TRBRI` is set equal to 1 in **icepack.settings**, the brine surface can move relative to the ice surface. Physically, this occurs when the ice is permeable and there is a nonzero pressure head: the difference between the brine height and the equilibrium sea surface. Brine height motion is computed in **icepack_brine.F90** from thermodynamic variables and the ice microstructural state deduced from internal bulk salinities and temperature. This tracer is required for the transport of vertically resolved biogeochemical tracers and is closely coupled to the z-salinity prognostic salinity model.

Vertical transport processes are, generally, a result of the brine motion. Therefore the vertical transport equations for biogeochemical tracers will be defined only where brine is present. This region, from the ice-ocean interface to the brine height, defines the domain of the vertical bio-grid. The resolution of the bio-grid is specified in **icepack.settings** by setting the variable `NBGCLYR`. A detailed description of the bio-grid is given in section *Grid and boundary conditions*. The ice microstructural state, determined in **icepack_brine.F90**, is computed from sea ice salinities and temperatures linearly interpolated to the bio-grid. When $h_b > h_i$, the upper surface brine is assumed to have the same temperature as the ice surface.

Brine height is transported horizontally as the fraction $f_{bri} = h_b/h_i$, a volume conserved tracer. Note that unlike the sea ice porosity, brine height fraction may be greater than 1 when $h_b > h_i$.

Changes to h_b occur from ice and snow melt, ice bottom boundary changes, and from pressure adjustments. The computation of h_b at $t + \Delta t$ is a two step process. First, h_b is updated from changes in ice and snow thickness, ie.

$$h'_b = h_b(t) + \Delta h_b|_{h_i, h_s}. \quad (2.112)$$

Second, pressure driven adjustments arising from meltwater flushing and snow loading are applied to h'_b . Brine flow due to pressure forces are governed by Darcy's equation

$$w = -\frac{\Pi^* \bar{\rho} g}{\mu} \frac{h_p}{h_i}. \quad (2.113)$$

The vertical component of the net permeability tensor Π^* is computed as

$$\Pi^* = \left(\frac{1}{h} \sum_{i=1}^N \frac{\Delta z_i}{\Pi_i} \right)^{-1} \quad (2.114)$$

where the sea ice is composed of N vertical layers with i th layer thickness Δz_i and permeability Π_i . The average sea ice density is $\bar{\rho}$ specified in **icepack_zbgc_shared.F90**. The hydraulic head is $h_p = h_b - h_{sl}$ where h_{sl} is the sea level given by

$$h_{sl} = \frac{\bar{\rho}}{\rho_w} h_i + \frac{\rho_s}{\rho_w} h_s. \quad (2.115)$$

Assuming constant h_i and h_s during Darcy flow, the rate of change of h_b is

$$\frac{\partial h_b}{\partial t} = -w h_p \quad (2.116)$$

where $w_o = \Pi^* \bar{\rho} g / (h_i \mu \phi_{top})$ and ϕ_{top} is the upper surface porosity. When the Darcy flow is downward into the ice ($w_o < 0$), then ϕ_{top} equals the sea ice porosity in the uppermost layer. However, when the flow is upwards into the snow, then ϕ_{top} equals the snow porosity `phi_snow` specified in **icepack_in**. If a negative number is specified for `phi_snow`, then the default value is used: `phi_snow = 1 - \rho_s / \rho_w`.

Since h_{sl} remains relatively unchanged during Darcy flow, (2.116) has the approximate solution

$$h_b(t + \Delta t) \approx h_{sl}(t + \Delta t) + [h'_b - h_{sl}(t + \Delta t)] \exp \{-w \Delta t\}. \quad (2.117)$$

The contribution $\Delta h_b|_{h_i, h_s}$ arises from snow and ice melt and bottom ice changes. Since the ice and brine bottom boundaries coincide, changes in the ice bottom from growth or melt, $(\Delta h_i)_{bot}$, equal the bottom brine boundary changes. The surface contribution from ice and snow melt, however, is opposite in sign. The ice contribution is as follows. If $h_i > h_b$ and the ice surface is melting, ie. $(\Delta h_i)_{top} < 0$, then meltwater increases the brine height:

$$(\Delta h_b)_{top} = \frac{\rho_i}{\rho_o} \cdot \begin{cases} -(\Delta h_i)_{top} & \text{if } |(\Delta h_i)_{top}| < h_i - h_b \\ h_i - h_b & \text{otherwise.} \end{cases} \quad (2.118)$$

For snow melt ($\Delta h_s < 0$), it is assumed that all snow meltwater contributes a source of surface brine. The total change from snow melt and ice thickness changes is

$$\Delta h_b|_{h_i, h_s} = (\Delta h_b)_{top} - (\Delta h_i)_{bot} - \frac{\rho_s}{\rho_o} \Delta h_s. \quad (2.119)$$

The above brine height calculation is used only when h_i and h_b exceed a minimum thickness, `thinS`, specified in **icepack_zbgc_shared.F90**. Otherwise

$$h_b(t + \Delta t) = h_b(t) + \Delta h_i \quad (2.120)$$

provided that $|h_{sl} - h_b| \leq 0.001$. This formulation ensures small Darcy velocities when h_b first exceeds `thinS`.

Both the volume fraction f_{bri} and the area-weighted brine height h_b are available for output.

$$\frac{\sum f_{bri} v_i}{\sum v_i}, \quad (2.121)$$

while `hbri` is comparable to `hi` (h_i)

$$\frac{\sum f_{bri} h_i a_i}{\sum a_i}, \quad (2.122)$$

where the sums are taken over thickness categories.

2.7.3 Sea ice ecosystem

There are two options for modeling biogeochemistry in sea ice: 1) a skeletal layer or bottom layer model that assumes biology and biological molecules are restricted to a single layer at the base of the sea ice; and 2) a vertically resolved model (zbgc) that allows for biogeochemical processes throughout the ice column. The two models may be run with the same suite of biogeochemical tracers and use the same module **algal_dyn** in **icepack_algae.F90** to determine the biochemical reaction terms for the tracers at each vertical grid level. In the case of the skeletal-layer model this is a single layer, while for zbgc there are NBGCLYR+1 vertical layers. The primary difference between the two schemes is in the vertical transport assumptions for each biogeochemical tracer. This includes the parameterizations of fluxes between ocean and ice.

In order to run with the skeletal-layer model, the code must be built with the following options in **icepack.settings**:

```
setenv TRBGCS 1    # set to 1 for skeletal layer tracers
setenv TRBGCZ 0    # set to 1 for zbgc tracers
```

For zbgc with 8 vertical layers:

```
setenv TRBRI 1     # set to 1 for brine height tracer
setenv TRBGCS 0    # set to 1 for skeletal layer tracers
setenv TRBGCZ 1    # set to 1 for zbgc tracers
setenv NBGCLYR 7   # number of zbgc layers
```

There are also environmental variables in **icepack.settings** that, in part, specify the complexity of the ecosystem and are used for both zbgc and the skeletal-layer model. These are 1) TRALG, the number of algal species; 2) TRDOC, the number of dissolved organic carbon groups; 3) TRDIC, the number of dissolved inorganic carbon groups (this is currently not yet implemented and should be set to 0); 4) TRDON, the number of dissolved organic nitrogen groups; 5) TRFEP, the number of particulate iron groups; and 6) TRFED, the number of dissolved iron groups. The current version of **algal_dyn** biochemistry has parameters for up to 3 algal species (diatoms, small phytoplankton and *Phaeocystis* sp, respectively), 2 DOC tracers (polysaccharids and lipids, respectively), 0 DIC tracers, 1 DON tracer (proteins/amino acids), 1 particulate iron tracer and 1 dissolved iron tracer. Note, for tracers with multiple species/groups, the order is important. For example, specifying TRALG = 1 will compute reaction terms using parameters specific to ice diatoms. However, many of these parameters can be modified in **icepack_in**.

The complexity of the algal ecosystem must be specified in both **icepack.settings** during the build and in the namelist, **icepack_in**. The procedure is equivalent for both the skeletal-layer model and zbgc. The namelist specification is described in detail in section *Vertical BGC* ("zbgc")

Biogeochemical upper ocean concentrations are initialized in the subroutine **icepack_init_ocean_conc** in **icepack_zbgc.F90** unless coupled to the ocean biogeochemistry. Silicate and nitrate may be read from a file. This option is specified in the namelist by setting the variables `bgc_data_type` to ISPOL or NICE. The location of forcing files is specified in `bgc_data_dir` and the filename is hardcoded in **icedrv_forcing** (NJ - needs to be updated).

Skeletal Layer BGC

In the skeletal layer model, biogeochemical processing is modelled as a single layer of reactive tracers attached to the sea ice bottom. Optional settings are available via the `zbgc_nml` namelist in **icepack_in**. In particular, `skl_bgc` must be true and `z_tracers` and `solve_zbgc` must both be false.

Skeletal tracers T_b are ice area conserved and follow the horizontal transport Equation (2.23). For each horizontal grid point, local biogeochemical tracer equations are solved in **icepack_algae.F90**. There are two types of ice-ocean tracer flux formulations: 1) 'Jin2006' modeled after the growth rate dependent piston velocity and 2) 'constant' modeled after a constant piston velocity. The formulation is specified in **icepack_in** by setting `bgc_flux_type` equal to 'Jin2006' or 'constant'.

In addition to horizontal advection and transport among thickness categories, biogeochemical tracers (T_b where $b = 1, \dots, N_b$) satisfy a set of local coupled equations of the form

$$\frac{dT_b}{dt} = w_b \frac{\Delta T_b}{\Delta z} + R_b(T_j : j = 1, \dots, N_b) \quad (2.123)$$

where R_b represents the nonlinear biochemical reaction terms (described in section [Reaction Equations](#)) and Δz is a length scale representing the molecular sublayer of the ice-ocean interface. Its value is absorbed in the piston velocity parameters. The piston velocity w_b depends on the particular tracer and the flux formulation.

For ‘Jin2006’, the piston velocity is a function of ice growth and melt rates. All tracers (algae included) flux with the same piston velocity during ice growth, $dh/dt > 0$:

$$w_b = -p_g \left| m_1 + m_2 \frac{dh}{dt} - m_3 \left(\frac{dh}{dt} \right)^2 \right| \quad (2.124)$$

with parameters m_1, m_2, m_3 and p_g defined in **skl_biogeochemistry** in **icepack_algae.F90**. For ice melt, $dh/dt < 0$, all tracers with the exception of ice algae flux with

$$w_b = p_m \left| m_2 \frac{dh}{dt} - m_3 \left(\frac{dh}{dt} \right)^2 \right| \quad (2.125)$$

with p_m defined in **skl_biogeochemistry**. The ‘Jin2006’ formulation also requires that for both expressions, $|w_b| \leq 0.9h_{sk}/\Delta t$. The concentration difference at the ice-ocean boundary for each tracer, ΔT_b , depends on the sign of w_b . For growing ice, $w_b < 0$, $\Delta T_b = T_b/h_{sk} - T_{io}$, where T_{io} is the ocean concentration of tracer i . For melting ice, $w_b > 0$, $\Delta T_b = T_b/h_{sk}$.

In ‘Jin2006’, the algal tracer (N_a) responds to ice melt in the same manner as the other tracers (2.125). However, this is not the case for ice growth. Unlike dissolved nutrients, algae are able to cling to the ice matrix and resist expulsion during desalination. For this reason, algal tracers do not flux between ice and ocean during ice growth unless the ice algal brine concentration is less than the ocean algal concentration (N_o). Then the ocean seeds the sea ice concentration according to

$$w_b \frac{\Delta N_a}{\Delta z} = \frac{N_o h_{sk} / \phi_{sk} - N_a}{\Delta t} \quad (2.126)$$

The ‘constant’ formulation uses a fixed piston velocity (PVC) for positive ice growth rates for all tracers except N_a . As in ‘Jin2006’, congelation ice growth seeds the sea ice algal population according to (2.126) when $N_a < N_o h_{sk} / \phi_{sk}$. For bottom ice melt, all tracers follow the prescription

$$w_b \frac{\Delta T_b}{\Delta z} = \begin{cases} T_b |dh_i/dt| / h_{sk} & \text{if } |dh_i/dt| \Delta t / h_{sk} < 1 \\ T_b / \Delta t & \text{otherwise.} \end{cases} \quad (2.127)$$

A detailed description of the biogeochemistry reaction terms is given in section [Reaction Equations](#).

Vertical BGC (“zbgc”)

In order to solve for the vertically resolved biogeochemistry, several flags in **icepack_in** must be true: a) **tr_brine**, b) **z_tracers**, and c) **solve_zbgc**.

- **tr_brine** = true turns on the dynamic brine height tracer, h_b , which defines the vertical domain of the biogeochemical tracers. z-Tracer horizontal transport is conserved on ice volume \times brine height fraction.
- **z_tracers** = true indicates use of vertically resolved biogeochemical and z-aerosol tracers. This flag alone turns on the vertical transport scheme but not the biochemistry.
- **solve_zbgc** = true turns on the biochemistry for the vertically resolved tracers and automatically turns on the algal nitrogen tracer flag **tr_bgc_N**. If false, **tr_bgc_N** is set false and any other biogeochemical tracers in use are transported as passive tracers. This is appropriate for the black carbon and dust aerosols specified by **tr_zaero** true.

In addition, a halodynamics scheme must also be used. The default thermo-halodynamics is mushy layer `ktherm` set to 2. An alternative uses the Bitz and Lipscomb thermodynamics `ktherm` set to 1 and `solve_zsal` true (referred to as “zsalinity”).

With the above flags, the default biochemistry is a simple algal-nitrate system: `tr_bgc_N` and `tr_bgc_Nit` are true. Options exist in **icepack_in** to use a more complicated ecosystem which includes up to three algal classes, two DOC groups, one DON pool, limitation by nitrate, silicate and dissolved iron, sulfur chemistry plus refractory humic material.

The **icepack_in** namelist options are described in the [Table of Namelist Inputs](#).

Vertically resolved z-tracers are brine- volume conserved and thus depend on both the ice volume and the brine height fraction tracer ($v_{in}f_b$). These tracers follow the conservation equations for multiply dependent tracers (see, for example Equation (2.69) where a_{pnd} is a tracer on $a_{lvt}a_i$)

The following sections describe the vertical transport equation for mobile tracers, the partitioning of tracers into mobile and stationary fractions and the biochemical reaction equations. The vertical bio-grid is described in the [Grid and boundary conditions](#) section.

Mobile and stationary phases

Purely mobile tracers are tracers which move with the brine and thus, in the absence of biochemical reactions, evolve like salinity. For vertical tracer transport of purely mobile tracers, the flux conserved quantity is the bulk tracer concentration multiplied by the ice thickness, i.e. $C = h\phi[c]$, where h is the ice thickness, ϕ is the porosity, and $[c]$ is the tracer concentration in the brine. ϕ , $[c]$ and C are defined on the interface bio grid (igrid):

$$\text{igrid}(k) = \Delta(k-1) \quad \text{for } k = 1 : n_b + 1 \quad \text{and } \Delta = 1/n_b.$$

The biogeochemical module solves the following equation:

$$\frac{\partial C}{\partial t} = \frac{\partial}{\partial x} \left\{ \left(\frac{v}{h} + \frac{w_f}{h\phi} - \frac{\tilde{D}}{h^2\phi^2} \frac{\partial \phi}{\partial x} \right) C + \frac{\tilde{D}}{h^2\phi} \frac{\partial C}{\partial x} \right\} + h\phi R([c]) \quad (2.128)$$

where $D_{in} = \tilde{D}/h^2 = (D + \phi D_m)/h^2$ and $R([c])$ is the nonlinear biogeochemical interaction term (see [25]).

The solution to (2.128) is flux-corrected and positive definite. This is accomplished using a finite element Galerkin discretization. Details are in [Flux-corrected, positive definite transport scheme](#).

In addition to purely mobile tracers, some tracers may also adsorb or otherwise adhere to the ice crystals. These tracers exist in both the mobile and stationary phases. In this case, their total brine concentration is a sum $c_m + c_s$ where c_m is the mobile fraction transported by equation (2.128) and c_s is fixed vertically in the ice matrix. The algae are an exception, however. We assume that algae in the stationary phase resist brine motion, but rather than being fixed vertically, these tracers maintain their relative position in the ice. Algae that adhere to the ice interior (bottom, surface), remain in the ice interior (bottom, surface) until release to the mobile phase.

In order to model the transfer between these fractions, we assume that tracers adhere (are retained) to the crystals with a time-constant of τ_{ret} , and release with a time constant τ_{rel} , i.e.

$$\begin{aligned} \frac{\partial c_m}{\partial t} &= -\frac{c_m}{\tau_{ret}} + \frac{c_s}{\tau_{rel}} \\ \frac{\partial c_s}{\partial t} &= \frac{c_m}{\tau_{ret}} - \frac{c_s}{\tau_{rel}} \end{aligned}$$

We use the exponential form of these equations:

$$c_m^{t+dt} = c_m^t \exp\left(-\frac{dt}{\tau_{ret}}\right) + c_s^t \left(1 - \exp\left[-\frac{dt}{\tau_{rel}}\right]\right)$$

$$c_s^{t+dt} = c_s^t \exp\left(-\frac{dt}{\tau_{rel}}\right) + c_m^t \left(1 - \exp\left[-\frac{dt}{\tau_{ret}}\right]\right)$$

The time constants are functions of the ice growth and melt rates (dh/dt). All tracers except algal nitrogen diatoms follow the simple case: when $dh/dt \geq 0$, then $\tau_{rel} \rightarrow \infty$ and τ_{ret} is finite. For $dh/dt < 0$, then $\tau_{ret} \rightarrow \infty$ and τ_{rel} is finite. In other words, ice growth promotes transitions to the stationary phase and ice melt enables transitions to the mobile phase.

The exception is the diatom pool. We assume that diatoms, the first algal nitrogen group, can actively maintain their relative position within the ice, i.e. bottom (interior, upper) algae remain in the bottom (interior, upper) ice, unless melt rates exceed a threshold. The namelist parameter `algal_vel` sets this threshold.

The variable `bgc_tracer_type` determines the mobile to stationary transition timescales for each z-tracer. It is multi-dimensional with a value for each z-tracer. For `bgc_tracer_type`(k) equal to -1, the kth tracer remains solely in the mobile phase. For `bgc_tracer_type` equal to 1, the tracer has maximal rates in the retention phase and minimal in the release. For `bgc_tracer_type` equal to 0, the tracer has maximal rates in the release phase and minimal in the retention. Finally for `bgc_tracer_type` equal to 0.5, minimum timescales are used for both transitions. Table [Types of Mobile and Stationary Transitions](#) summarizes the transition types. The tracer types are: `algatype_diatoms`, `algatype_sp` (small plankton), `algatype_phaeo` (*phaeocystis*), `nitratetype`, `ammoniumtype`, `silicatetype`, `dmsptype`, `dmspdtype`, `humtype`, `doctype_s` (saccharids), `doctype_l` (lipids), `dontype_protein`, `fedtype_l`, `feptype_l`, `zaerotype_bc1` (black carbon class 1), `zaerotype_bc2` (black carbon class 2), and four dust classes, `zaerotype_dustj`, where j takes values 1 to 4. These may be modified to increase or decrease retention. Another option is to alter the minimum `tau_min` and maximum `tau_max` timescales which would impact all the z-tracers.

Table 2.3: Types of Mobile and Stationary Transitions

<code>bgc_tracer_type</code>	τ_{ret}	τ_{rel}	Description
-1.0	∞	0	entirely in the mobile phase
0.0	min	max	retention dominated
1.0	max	min	release dominated
0.5	min	min	equal but rapid exchange
2.0	max	max	equal but slow exchange

The fraction of a given tracer in the mobile phase is independent of ice depth and stored in the tracer variable `zbgc_frac`. The horizontal transport of this tracer is conserved on brine volume and so is dependent on two tracers: brine height fraction (f_b) and ice volume (v_{in}). The conservation equations are given by

$$\frac{\partial}{\partial t}(f_b v_{in}) + \nabla \cdot (f_b v_{in} \mathbf{u}) = 0.$$

The tracer, `zbgc_frac`, is initialized to 1 during new ice formation, because all z-tracers are initially in the purely mobile phase. Similarly, as the ice melts, z-tracers return to the mobile phase. Very large release timescales will prevent this transition and could result in an unphysically large accumulation during the melt season.

Flux-corrected, positive definite transport scheme

Numerical solution of the vertical tracer transport equation is accomplished using the finite element Galerkin discretization. Multiply (2.128) by “w” and integrate by parts

$$\begin{aligned} & \int_h \left[w \frac{\partial C}{\partial t} - \frac{\partial w}{\partial x} \left(- \left[\frac{v}{h} + \frac{w_f}{h\phi} \right] C + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} C - \frac{D_{in}}{\phi} \frac{\partial C}{\partial x} \right) \right] dx \\ & + w \left(- \left[\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi} \right] C + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} C - \frac{D_{in}}{\phi} \frac{\partial C}{\partial x} \right) \Big|_{bottom} + w \left[\frac{1}{h} \frac{dh_t}{dt} + \frac{w_f}{h\phi} \right] C|_{top} = 0 \end{aligned}$$

The bottom boundary condition indicated by $|_{bottom}$ satisfies

$$-w \left(- \left[\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi} \right] C + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} C - \frac{D_{in}}{\phi} \frac{\partial C}{\partial x} \right) \Big|_{bottom} = w \left[\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi_{N+1}} \right] (C_{N+2} \text{ or } C_{N+1}) - w \frac{D_{in}}{\phi_{N+1}(\Delta h + g_o)} (C_{N+1} - C_{N+2})$$

where $C_{N+2} = h\phi_{N+1}[c]_{ocean}$ and $w = 1$ at the bottom boundary and the top. The component C_{N+2} or C_{N+1} depends on the sign of the advection boundary term. If $dh_b + w_f/\phi > 0$ then use C_{N+2} otherwise C_{N+1} .

Define basis functions as linear piecewise, with two nodes (boundary nodes) in each element. Then for $i > 1$ and $i < N + 1$

$$w_i(x) = \begin{cases} 0 & x < x_{i-1} \\ (x - x_{i-1})/\Delta & x_{i-1} < x \leq x_i \\ 1 - (x - x_i)/\Delta & x_i \leq x < x_{i+1} \\ 0, & x \geq x_{i+1} \end{cases}$$

For $i = 1$

$$w_1(x) = \begin{cases} 1 - x/\Delta & x < x_2 \\ 0, & x \geq x_2 \end{cases}$$

and $i = N + 1$

$$w_{N+1}(x) = \begin{cases} 0, & x < x_N \\ (x - x_N)/\Delta & x \geq x_N \end{cases}$$

Now assume a form

$$C_h = \sum_j^{N+1} c_j w_j$$

Then

$$\begin{aligned} \int_h C_h dx &= c_1 \int_0^{x_2} \left(1 - \frac{x}{\Delta}\right) dx + c_{N+1} \int_{x_N}^{x_{N+1}} \frac{x - x_N}{\Delta} dx \\ &+ \sum_{j=2}^N c_j \left\{ \int_{x_{j-1}}^{x_j} \frac{x - x_{j-1}}{\Delta} dx + \int_{x_j}^{x_{j+1}} \left[1 - \frac{(x - x_j)}{\Delta}\right] dx \right\} \\ &= \Delta \left[\frac{c_1}{2} + \frac{c_{N+1}}{2} + \sum_{j=2}^N c_j \right] \end{aligned}$$

Now this approximate solution form is substituted into the variational equation with $w = w_h \in \{w_j\}$

$$\begin{aligned} 0 &= \int_h \left[w_h \frac{\partial C_h}{\partial t} - \frac{\partial w_h}{\partial x} \left(\left[-\frac{v}{h} - \frac{w_f}{h\phi} + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} \right] C_h - \frac{D_{in}}{\phi} \frac{\partial C_h}{\partial x} \right) \right] dx \\ &+ w_h \left(- \left[\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi} \right] C_h + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} C - \frac{D_{in}}{\phi} \frac{\partial C_h}{\partial x} \right) \Big|_{bottom} + w_h \left[\frac{1}{h} \frac{dh_t}{dt} + \frac{w_f}{h\phi} \right] C_h \Big|_{top} \end{aligned}$$

The result is a linear matrix equation

$$M_{jk} \frac{\partial C_k(t)}{\partial t} = [K_{jk} + S_{jk}] C_k(t) + q_{in}$$

where

$$\begin{aligned}
 M_{jk} &= \int_h w_j(x) w_k(x) dx \\
 K_{jk} &= \left[-\frac{v}{h} - \frac{w_f}{h\phi} + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} \right] \int_h \frac{\partial w_j}{\partial x} w_k dx \\
 &\quad - w_j \left(-\left[\frac{v}{h} + \frac{w_f}{h\phi_k} \right] w_k + \frac{D_{in}}{\phi^2} \frac{\partial \phi_k}{\partial x} w_k - \frac{D_{in}}{\phi_k} \frac{\partial w_k}{\partial x} \right) \Big|_{bot} \\
 &= -V_k \int_h \frac{\partial w_j}{\partial x} w_k dx - w_j \left(-V_k w_k - \frac{D_{in}}{\phi_k} \frac{\partial w_k}{\partial x} \right) \Big|_{bot} \\
 S_{jk} &= -\frac{D_{in}}{\phi_k} \int_h \frac{\partial w_j}{\partial x} \cdot \frac{\partial w_k}{\partial x} dx \\
 q_{in} &= -VC_t w_j(x)|_t
 \end{aligned}$$

and $C_{N+2} = h\phi_{N+1}[c]_{ocean}$.

For the top condition q_{in} is applied to the upper value C_2 when $VC_t < 0$, i.e. q_{in} is a source.

Compute the M_{jk} integrals:

$$\begin{aligned}
 M_{jj} &= \int_{x_{j-1}}^{x_j} \frac{(x - x_{j-1})^2}{\Delta^2} dx + \int_{x_j}^{x_{j+1}} \left[1 - \frac{(x - x_j)}{\Delta} \right]^2 dx = \frac{2\Delta}{3} \quad \text{for } 1 < j < N + 1 \\
 M_{11} &= \int_{x_1}^{x_2} \left[1 - \frac{(x - x_2)}{\Delta} \right]^2 dx = \frac{\Delta}{3} \\
 M_{N+1,N+1} &= \int_{x_N}^{x_{N+1}} \frac{(x - x_N)^2}{\Delta^2} dx = \frac{\Delta}{3}
 \end{aligned}$$

Off diagonal components:

$$\begin{aligned}
 M_{j,j+1} &= \int_{x_j}^{x_{j+1}} \left[1 - \frac{(x - x_j)}{\Delta} \right] \left[\frac{x - x_j}{\Delta} \right] dx = \frac{\Delta}{6} \quad \text{for } j < N + 1 \\
 M_{j,j-1} &= \int_{x_{j-1}}^{x_j} \left[\frac{x - x_{j-1}}{\Delta} \right] \left[1 - \frac{(x - x_{j-1})}{\Delta} \right] dx = \frac{\Delta}{6} \quad \text{for } j > 1
 \end{aligned}$$

Compute the K_{jk} integrals:

$$\begin{aligned}
 K_{jj} &= k'_{jj} \left[\int_{x_{j-1}}^{x_j} \frac{\partial w_j}{\partial x} w_j dx + \int_{x_j}^{x_{j+1}} \frac{\partial w_j}{\partial x} w_j dx \right] \\
 &= \frac{1}{2} + -\frac{1}{2} = 0 \quad \text{for } 1 < j < N + 1 \\
 K_{11} &= -\frac{k'_{11}}{2} = \frac{1}{2} \left[\frac{v}{h} + \frac{w_f}{h\phi} \right] \\
 K_{N+1,N+1} &= \frac{k'_{N+1,N+1}}{2} + \min \left[0, \left(\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi_{N+1}} \right) \right] - \frac{D_{in}}{\phi_{N+1}(g_o/h)} \\
 &= \left[-\frac{v}{h} - \frac{w_f}{h\phi} + \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} \right] \frac{1}{2} + \min \left[0, \left(\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi_{N+1}} \right) \right] - \frac{D_{in}}{\phi_{N+1}(g_o/h)}
 \end{aligned}$$

Off diagonal components:

$$\begin{aligned}
 K_{j(j+1)} &= k'_{j(j+1)} \int_{x_j}^{x_{j+1}} \frac{\partial w_j}{\partial x} w_{j+1} dx = -k'_{j(j+1)} \int_{x_j}^{x_{j+1}} \frac{(x - x_j)}{\Delta^2} dx \\
 &= -\frac{k'_{j(j+1)} \Delta^2}{2} = -\frac{k'_{j(j+1)}}{2} = p5 * \left[\frac{v}{h} + \frac{w_f}{h\phi} - \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} \right]_{(j+1)} \quad \text{for } j < N + 1 \\
 K_{j(j-1)} &= k'_{j(j-1)} \int_{x_{j-1}}^{x_j} \frac{\partial w_j}{\partial x} w_{j-1} dx = k'_{j(j-1)} \int_{x_{j-1}}^{x_j} \left[1 - \frac{(x - x_{j-1})}{\Delta^2} \right] dx \\
 &= \frac{k'_{j(j-1)} \Delta^2}{2} = \frac{k'_{j(j-1)}}{2} = -p5 * \left[\frac{v}{h} + \frac{w_f}{h\phi} - \frac{D_{in}}{\phi^2} \frac{\partial \phi}{\partial x} \right]_{(j-1)} \quad \text{for } j > 1
 \end{aligned}$$

For $K_{N+1,N}$, there is a boundary contribution:

$$K_{N+1,N} = \frac{k'_{N+1(N)}}{2} - \frac{D_N}{\Delta \phi_N}$$

The bottom condition works if $C_{bot} = h\phi_{N+2}[c]_{ocean}$, ϕ^2 is $\phi_{N+1}\phi_{N+2}$ and

$$\left. \frac{\partial \phi}{\partial x} \right|_{bot} = \frac{\phi_{N+2} - \phi_N}{2\Delta};$$

then the $D_{N+1}/\phi_{N+1}/\Delta$ cancels properly with the porosity gradient. In general

$$\left. \frac{\partial \phi}{\partial x} \right|_k = \frac{\phi_{k+2} - \phi_k}{2\Delta}.$$

When evaluating the integrals for the diffusion term, we will assume that D/ϕ is constant in an element. For $D_{in}/i\phi$ defined on interface points, $D_1 = 0$ and for $j = 2, \dots, N$ $D_j/b\phi_j = (D_{in}(j) + D_{in}(j+1))/(i\phi_j + i\phi_{j+1})$. Then the above integrals will be modified as follows:

Compute the S_{jk} integrals:

$$\begin{aligned}
 S_{jj} &= - \left[\frac{D_{j-1}}{b\phi_{j-1}} \int_{x_{j-1}}^{x_j} \left(\frac{\partial w_j}{\partial x} \right)^2 dx + \frac{D_j}{b\phi_j} \int_{x_j}^{x_{j+1}} \left(\frac{\partial w_j}{\partial x} \right)^2 dx \right] \\
 &= -\frac{1}{\Delta} \left[\frac{D_{j-1}}{b\phi_{j-1}} + \frac{D_j}{b\phi_j} \right] \quad \text{for } 1 < j < N + 1 \\
 S_{11} &= \frac{s'_{11}}{\Delta} = 0 \\
 S_{N+1,N+1} &= \frac{s'_{N+1,N+1}}{\Delta} = -\frac{(D_N)}{b\phi_N \Delta}
 \end{aligned}$$

Compute the off-diagonal components of S_{jk} :

$$\begin{aligned}
 S_{j(j+1)} &= s'_{j(j+1)} \int_{x_j}^{x_{j+1}} \frac{\partial w_j}{\partial x} \frac{\partial w_{j+1}}{\partial x} dx = -\frac{s'_{j(j+1)}}{\Delta} = \frac{D_j}{b\phi_j \Delta} \quad \text{for } j < N + 1 \\
 S_{j(j-1)} &= s'_{j(j-1)} \int_{x_{j-1}}^{x_j} \frac{\partial w_j}{\partial x} \frac{\partial w_{j-1}}{\partial x} dx = -\frac{s'_{j(j-1)}}{\Delta} = \frac{D_{j-1}}{b\phi_{j-1} \Delta} \quad \text{for } j > 1
 \end{aligned}$$

We assume that $D/\phi^2 \partial \phi / \partial x$ is constant in the element i . If D/ϕ_j is constant, and $\partial \phi / \partial x$ is constant then both the Darcy and D terms go as ϕ^{-1} . Then $\phi = (\phi_j - \phi_{j-1})(x - x_j)/\Delta + \phi_j$ and $m = (\phi_j - \phi_{j-1})/\Delta$ and $b = \phi_j - m x_j$.

The first integral contribution to the Darcy term is:

$$\begin{aligned}
K_{jj}^1 &= \frac{-1}{\Delta^2} \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \int_{j-1}^j (x - x_{j-1}) \frac{1}{mx + b} dx \\
&= - \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta^2} \left[\int_{j-1}^j \frac{x}{mx + b} dx - x_{j-1} \int_{j-1}^j \frac{1}{mx + b} dx \right] \\
&= - \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta^2} \left[\frac{mx - b \log(b + mx)}{m^2} - x_{j-1} \frac{\log(b + mx)}{m} \right]_{x_{j-1}}^{x_j} \\
&= - \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta_\phi} \left[1 + \log \left(\frac{\phi_j}{\phi_{j-1}} \right) - \frac{\phi_j}{\Delta_\phi} \log \left(\frac{\phi_j}{\phi_{j-1}} \right) \right] \\
&= - \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta_\phi} \left[1 + \frac{\phi_{j-1}}{\Delta_\phi} \log \left(\frac{\phi_j}{\phi_{j-1}} \right) \right] \\
K_{jj}^2 &= \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta} \int_{x_j}^{x_{j+1}} \left[1 - \frac{(x - x_j)}{\Delta} \right] \frac{1}{mx + b} dx \\
&= \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta} \left[\frac{(b + m(x_j + \Delta)) \log(b + mx) - mx}{\Delta m^2} \right]_{x_j}^{x_{j+1}} \\
&= \left(\frac{w_f}{h} - \frac{D}{\phi} \frac{\partial \phi}{\partial x} \right) \frac{1}{\Delta_\phi} \left[1 - \frac{\phi_{j+1}}{\Delta_\phi} \log \left(\frac{\phi_{j+1}}{\phi_j} \right) \right]
\end{aligned}$$

Now $m = (\phi_{j+1} - \phi_j)/\Delta$ and $b = \phi_{j+1} - mx_{j+1}$.

Source terms $q_{bot} = q_{N+1}$ and $q_{top} = q_1$ (both positive)

$$\begin{aligned}
q_{bot} &= \max \left[0, \left(\frac{1}{h} \frac{dh_b}{dt} + \frac{w_f}{h\phi_{N+1}} \right) \right] C|_{bot} + \frac{D_{in}}{\phi_{N+1}(g_o/h)} C|_{bot} \\
C|_{bot} &= \phi_{N+1}[c]_{ocean}
\end{aligned}$$

where g_o is not zero.

$$\begin{aligned}
q_{in} &= -\min \left[0, \left(\frac{1}{h} \frac{dh_t}{dt} + \frac{w_f}{h\phi} \right) C|_{top} \right] \\
C|_{top} &= h[c]_o \phi_{min}
\end{aligned}$$

Calculating the low order solution:

1) Find the lumped mass matrix $M_l = \text{diag}\{m_i\}$

$$\begin{aligned}
m_j &= \sum_i m_{ji} = m_{j(j+1)} + m_{j(j-1)} + m_{jj} \\
&= \frac{\Delta}{6} + \frac{\Delta}{6} + \frac{2\Delta}{3} = \Delta \quad \text{for } 1 < j < N+1 \\
m_1 &= m_{11} + m_{12} = \frac{\Delta}{3} + \frac{\Delta}{6} = \frac{\Delta}{2} \\
m_{N+1} &= m_{N+1,N} + m_{N+1,N+1} = \frac{\Delta}{6} + \frac{\Delta}{3} = \frac{\Delta}{2}
\end{aligned}$$

2. Define artificial diffusion D_a

$$\begin{aligned}
d_{j,(j+1)} &= \max\{-k_{j(j+1)}, 0, -k_{(j+1)j}\} = d_{(j+1)j} \\
d_{jj} &= -\sum_{i \neq j} d_{ji}
\end{aligned}$$

3. Add artificial diffusion to K : $L = K + D_a$.

4. Solve for the low order predictor solution:

$$(M_l - \Delta t[L + S])C^{n+1} = M_l C^n + \Delta t q$$

Conservations terms for the low order solution are:

$$\begin{aligned} \int [C^{n+1} - C^n] w(x) dx &= \Delta \left[\frac{c_1^{n+1} - c_1^n}{2} + \frac{c_{N+1}^{n+1} - c_{N+1}^n}{2} + \sum_{j=2}^N (c_j^{n+1} - c_j^n) \right] \\ &= \Delta t [q_{bot} + q_{in} + (K_{N+1,N+1} + K_{N,N+1})C_{N+1}^{n+1} + (K_{1,1} + K_{2,1})C_1^{n+1}] \end{aligned}$$

Now add the antidiffusive flux: compute the F matrix using the low order solution c^{n+1} . Diagonal components are zero. For $i \neq j$

$$f_{ij} = m_{ij} \left[\frac{\Delta c_i}{\Delta t} - \frac{\Delta c_j}{\Delta t} + d_{ij}(c_i^{n+1} - c_j^{n+1}) \right].$$

Reaction Equations

The biogeochemical reaction terms for each biogeochemical tracer (see Table *Biogeochemical Tracers* for tracer definitions) are defined in **icepack_algae.F90** in the subroutine *algal_dyn*. The same set of equations is used for the bottom layer model (when `skl_bgc` is true) and the multi-layer biogeochemical model (when `z_tracers` and `solve_zbgc` are true).

Table 2.4: *Biogeochemical Tracers*

Text Variable	Variable in code	flag	Description	units
N (1)	Nin(1)	<i>tr_bgc_N</i>	diatom	<i>mmol N/m³</i>
N (2)	Nin(2)	<i>tr_bgc_N</i>	small phytoplankton	<i>mmol N/m³</i>
N (3)	Nin(3)	<i>tr_bgc_N</i>	<i>Phaeocystis sp</i>	<i>mmol N/m³</i>
DOC (1)	DOCin(1)	<i>tr_bgc_DOC</i>	polysaccharids	<i>mmol C/m³</i>
DOC (2)	DOCin(2)	<i>tr_bgc_DOC</i>	lipids	<i>mmol C/m³</i>
DON	DONin(1)	<i>tr_bgc_DON</i>	proteins	<i>mmol C/m³</i>
fed	Fedin(1)	<i>tr_bgc_Fe</i>	dissolved iron	<i>μ Fe/m³</i>
fep	Fepin(1)	<i>tr_bgc_Fe</i>	particulate iron	<i>μ Fe/m³</i>
NO ₃	Nitin	<i>tr_bgc_Nit</i>	NO ₃	<i>mmol N/m³</i>
NH ₄	Amin	<i>tr_bgc_Am</i>	NH ₄	<i>mmol N/m³</i>
SiO ₃	Silin	<i>tr_bgc_Sil</i>	SiO ₂	<i>mmol Si/m³</i>
DMSPp	DMSPpin	<i>tr_bgc_DMS</i>	particulate DMSP	<i>mmol S/m³</i>
DMSPd	DMSPdin	<i>tr_bgc_DMS</i>	dissolved DMSP	<i>mmol S/m³</i>
DMS	DMSin	<i>tr_bgc_DMS</i>	DMS	<i>mmol S/m³</i>
PON	PON ^a	<i>tr_bgc_PON</i>	passive mobile tracer	<i>mmol N/m³</i>
hum	hum ^{ab}	<i>tr_bgc_hum</i>	passive sticky tracer	<i>mmol /m³</i>
BC (1)	zaero(1) ^a	<i>tr_zaero</i>	black carbon species 1	<i>kg /m³</i>
BC (2)	zaero(2) ^a	<i>tr_zaero</i>	black carbon species 2	<i>kg /m³</i>
dust (1)	zaero(3) ^a	<i>tr_zaero</i>	dust species 1	<i>kg /m³</i>
dust (2)	zaero(4) ^a	<i>tr_zaero</i>	dust species 2	<i>kg /m³</i>
dust (3)	zaero(5) ^a	<i>tr_zaero</i>	dust species 3	<i>kg /m³</i>
dust (4)	zaero(6) ^a	<i>tr_zaero</i>	dust species 4	<i>kg /m³</i>

^a not modified in *algal_dyn*

^b may be in C or N units depending on the ocean concentration

The biochemical reaction term for each algal species has the form:

$$\Delta N/dt = R_N = \mu(1 - f_{graze} - f_{res}) - M_{ort}$$

where μ is the algal growth rate, M_{ort} is a mortality loss, f_{graze} is the fraction of algal growth that is lost to predatory grazing, and f_{res} is the fraction of algal growth lost to respiration. Algal mortality is temperature dependent and limited by a maximum loss rate fraction (l_{max}):

$$M_{ort} = \min(l_{max}[N], m_{pre} \exp\{m_T(T - T_{max})\}[N])$$

Note, $[\cdot]$ denotes brine concentration.

Nitrate and ammonium reaction terms are given by

$$\begin{aligned} \Delta NO_3/dt &= R_{NO_3} = [NH_4]k_{nitr} - U_{NO_3}^{tot} \\ \Delta NH_4/dt &= R_{NH_4} = -[NH_4]k_{nitr} - U_{NH_4}^{tot} + (f_{ng}f_{graze}(1 - f_{gs}) + f_{res})\mu^{tot} \\ &\quad + f_{nm}M_{ort} \\ &= -[NH_4]k_{nitr} - U_{NH_4}^{tot} + N_{remin} \end{aligned}$$

where the uptake U^{tot} and algal growth μ^{tot} are accumulated totals for all algal species. k_{nitr} is the nitrification rate and f_{ng} and f_{nm} are the fractions of grazing and algal mortality that are remineralized to ammonium and f_{gs} is the fraction of grazing spilled or lost. Algal growth and nutrient uptake terms are described in more detail in [Algal growth and nutrient uptake](#).

Dissolved organic nitrogen satisfies the equation

$$\Delta DON/dt = R_{DON} = f_{dg}f_{gs}f_{graze}\mu^{tot} - [DON]k_{nb}$$

With a loss from bacterial degradation (rate k_{nb}) and a gain from spilled grazing that does not enter the NH_4 pool.

A term Z_{oo} closes the nitrogen cycle by summing all the excess nitrogen removed as zooplankton/bacteria in a timestep. This term is not a true tracer, i.e. not advected horizontally with the ice motion, but provides a diagnostic comparison of the amount of N removed biogeochemically from the ice $N-NO_3-NH_4-DON$ cycle at each timestep.

$$Z_{oo} = [(1 - f_{ng}(1 - f_{gs}) - f_{dg}f_{gs})f_{graze}\mu^{tot}dt + (1 - f_{nm})M_{ort}dt + [DON]k_{nb}dt]$$

Dissolved organic carbon may be divided into polysaccharids and lipids. Parameters are two dimensional (indicated by superscript i) with index 1 corresponding to polysaccharids and index 2 appropriate for lipids. The DOC^i equation is:

$$\Delta DOC^i/dt = R_{DOC}^i = f_{cg}^i f_{ng} \mu^{tot} + R_{c:n}^i M_{ort} - [DOC]^i k_{cb}^i$$

Silicate has no biochemical source terms within the ice and is lost only through algal uptake:

$$\Delta SiO_3/dt = R_{SiO_3} = -U_{SiO_3}^{tot}$$

Dissolved iron has algal uptake and remineralization pathways. In addition, fed may be converted to or released from the particulate iron pool depending on the dissolve iron (fed) to polysaccharid ($DOC(1)$) concentration ratio. If this ratio exceeds a maximum value $r_{fed:doc}^{max}$ then the change in concentration for dissolved and particulate iron is

$$\begin{aligned} \Delta_{fe} fed/dt &= -[fed]/\tau_{fe} \\ \Delta_{fe} fep/dt &= [fed]/\tau_{fe} \end{aligned}$$

For values less than $r_{fed:doc}^{max}$

$$\begin{aligned} \Delta_{fe} fed/dt &= [fep]/\tau_{fe} \\ \Delta_{fe} fep/dt &= -[fep]/\tau_{fe} \end{aligned}$$

Very long timescales τ_{fe} will remove this source/sink term. The default value is currently set at 3065 days to turn off this dependency (any large number will do to turn it off). 61-65 days is a more realistic option (Parekh et al., 2004).

The full equation for fed including uptake and remineralization is

$$\Delta_{fed}/dt = R_{fed} = -U_{fed}^{tot} + f_{fa}R_{fe:n}N_{remin} + \Delta_{fe}fed/dt$$

Particulate iron also includes a source term from algal mortality and grazing that is not immediately bioavailable. The full equation for fep is

$$\Delta_{fep}/dt = R_{fep} = R_{fe:n}[Z_{oo}/dt + (1 - f_{fa})N_{remin} + \Delta_{fe}fep/dt$$

The sulfur cycle includes DMS and dissolved DMSP (DMSPd). Particulate DMSP is assumed to be proportional to the algal concentration, i.e. $DMSPp = R_{s:n}^i N^i$ for algal species i . For DMSP and DMS,

$$\begin{aligned}\Delta_{DMSPd}/dt &= R_{DMSPd} = R_{s:n}[f_{sr}f_{res}\mu^{tot} + f_{nm}M_{ort}] - [DMSPd]/\tau_{dmsp} \\ \Delta_{DMS}/dt &= R_{DMS} = y_{dms}[DMSPd]/\tau_{dmsp} - [DMS]/\tau_{dms}\end{aligned}$$

See *BGC Tuning Parameters* for a more complete list and description of biogeochemical parameters.

Algal growth and nutrient uptake

Nutrient limitation terms are defined in the simplest ecosystem for NO_3 . If the appropriate tracer flags are true, then limitation terms may also be found for NH_4 , SiO_3 , and fed

$$\begin{aligned}NO_{3lim} &= \frac{[NO_3]}{[NO_3] + K_{NO_3}} \\ NH_{4lim} &= \frac{[NH_4]}{[NH_4] + K_{NH_4}} \\ N_{lim} &= \min(1, NO_{3lim} + NH_{4lim}) \\ SiO_{3lim} &= \frac{[SiO_3]}{[SiO_3] + K_{SiO_3}} \\ fed_{lim} &= \frac{[fed]}{[fed] + K_{fed}}\end{aligned}$$

Light limitation L_{lim} is defined in the following way: $I_{sw}(z)$ (in W/m^2) is the shortwave radiation at the ice level and the optical depth is proportional to the chlorophyll concentration, $op_{dep} = chl_{abs} [Chl*a*]$. If ($op_{dep} > op_{min}$) then

$$I_{avg} = I_{sw}(1 - \exp(-op_{dep}))/op_{dep}$$

otherwise $I_{avg} = I_{sw}$.

$$L_{lim} = (1 - \exp(-\alpha I_{avg})) \exp(-\beta I_{avg})$$

The maximal algal growth rate before limitation is

$$\begin{aligned}\mu_o &= \mu_{max} \exp(\mu_T \Delta T) f_{sal}[N] \\ \mu' &= \min(L_{lim}, N_{lim}, SiO_{3lim}, fed_{lim}) \mu_o\end{aligned}$$

where μ' is the initial estimate of algal growth rate for a given algal species and ΔT is the difference between the local temperature and the maximum (in this case $T_{max} = 0^\circ C$).

The initial estimate of the uptake rate for silicate and iron is

$$\begin{aligned}\tilde{U}_{\text{SiO}_3} &= R_{si:n} \mu' \\ \tilde{U}_{\text{fed}} &= R_{fe:n} \mu'\end{aligned}$$

For nitrogen uptake, we assume that ammonium is preferentially acquired by algae. To determine the nitrogen uptake needed for each algal growth rate of μ , first determine the “potential” uptake rate of ammonium:

$$U'_{\text{NH}_4} = \text{NH}_{4\text{lim}} \mu_o$$

Then

$$\begin{aligned}\tilde{U}_{\text{NH}_4} &= \min(\mu', U'_{\text{NH}_4}) \\ \tilde{U}_{\text{NO}_3} &= \mu' - \tilde{U}_{\text{NH}_4}\end{aligned}$$

We require that each rate not exceed a maximum loss rate l_{max}/dt . This is particularly important when multiple species are present. In this case, the accumulated uptake rate for each nutrient is found and the fraction (fU^i) of uptake due to algal species i is saved. Then the total uptake rate is compared with the maximum loss condition. For example, the net uptake of nitrate when there are three algal species is

$$\tilde{U}_{\text{NO}_3}^{\text{tot}} = \sum_{i=1}^3 \tilde{U}_{\text{NO}_3}^i \quad .$$

Then the uptake fraction for species i and the adjusted total uptake is

$$\begin{aligned}fU_{\text{NO}_3}^i &= \frac{\tilde{U}_{\text{NO}_3}^i}{\tilde{U}_{\text{NO}_3}^{\text{tot}}} \\ U_{\text{NO}_3}^{\text{tot}} &= \min(\tilde{U}_{\text{NO}_3}^{\text{tot}}, l_{\text{max}}[\text{NO}_3]/dt)\end{aligned}$$

Now, for each algal species the nitrate uptake is

$$U_{\text{NO}_3}^i = fU_{\text{NO}_3}^i U_{\text{NO}_3}^{\text{tot}}$$

Similar expressions are found for all potentially limiting nutrients. Then the true growth rate for each algal species i is

$$\mu^i = \min(U_{\text{SiO}_3}^i/R_{si:n}, U_{\text{NO}_3}^i + U_{\text{NH}_4}^i, U_{\text{fed}}^i/R_{fe:n})$$

Preferential ammonium uptake is assumed once again and the remaining nitrogen is taken from the nitrate pool.

3.1 Implementation

Icepack is written in FORTRAN90 and runs on platforms using UNIX, LINUX, and other operating systems. The code is not parallelized. (CHANGE IF OPENMP IS IMPLEMENTED)

Icepack consists of the sea ice column physics code, contained in the **columnphysics/** directory, and a **configuration/** directory that includes a driver for testing the column physics and a set of scripts for configuring the tests. Icepack is designed such that the column physics code may be used by a host sea ice model without direct reference to the driver or scripts, although these may be consulted for guidance when coupling the column physics code to the host sea ice model (**CICE** may also be useful for this.) Information about the interface between the column physics and the driver or host sea ice model is located in the *Initialization and Forcing* section.

3.1.1 Directory structure

The present code distribution includes source code for the column physics, source code for the driver, and the scripts. Forcing data is available from the ftp site. The directory structure of Icepack is as follows. All columnphysics filename have a prefix of icepack_ and all driver files are prefixed with icedrv_*.

LICENSE.pdf license and policy for using and sharing the code

DistributionPolicy.pdf license and policy for using and sharing the code

README.md basic information and pointers

columnphysics/ directory for columnphysics source code, see *Icepack Column Physics*

configuration/scripts/ directory of support scripts, see *Scripts Implementation*

configuration/driver/ directory of icepack driver code, see *Driver Implementation*

doc/ documentation

icepack.setup main icepack script for creating cases

A case (compile) directory is created upon initial execution of the script **icepack.setup** at the user-specified location provided after the -c flag. Executing the command `./icepack.setup -h` provides helpful information for this tool.

3.1.2 Grid and boundary conditions

The driver configures a collection of grid cells on which the column physics code will be run. This “horizontal” grid is a vector of length n_x , with a minimum length of 4. The grid vector is initialized with different sea ice conditions,

such as open water, a uniform slab of ice, a multi-year ice thickness distribution with snow, and land. For simplicity, the same forcing values are applied to all grid cells.

Icepack includes two vertical grids. The basic vertical grid contains `nilyr` equally spaced grid cells. History variables available for column output are ice and snow temperature, `Tinz` and `Tsnz`. These variables also include thickness category as a fourth dimension.

In addition, there is a bio-grid that can be more finely resolved and includes additional nodes for boundary conditions. It is used for solving the brine height variable h_b and for discretizing the vertical transport equations of biogeochemical tracers. The bio-grid is a non-dimensional vertical grid which takes the value zero at h_b and one at the ice–ocean interface. The number of grid levels is specified during compilation by setting the variable `NBGCLYR` equal to an integer (n_b).

Ice tracers and microstructural properties defined on the bio-grid are referenced in two ways: as `bgrid = $n_b + 2$` points and as `igrid = $n_b + 1$` points. For both `bgrid` and `igrid`, the first and last points reference h_b and the ice–ocean interface, respectively, and so take the values 0 and 1, respectively. For `bgrid`, the interior points $[2, n_b + 1]$ are spaced at $1/n_b$ intervals beginning with $bgrid(2) = 1/(2n_b)$. The `igrid` interior points $[2, n_b]$ are also equidistant with the same spacing, but physically coincide with points midway between those of `bgrid`.

3.1.3 Initialization and Forcing

Icepack’s parameters and variables are initialized in several steps. Many constants and physical parameters are set in **icepack_parameters.F90**. In the current driver implementation, a namelist file is read to setup the model. Namelist values are given default values in the code, which may then be changed when the input file **icepack_in** is read. Other physical constants, numerical parameters, and variables are first set in initialization routines for each ice model component or module. Then, if the ice model is being restarted from a previous run, core variables are read and reinitialized in *restartfile*, while tracer variables needed for specific configurations are read in separate restart routines associated with each tracer or specialized parameterization. Finally, albedo and other quantities dependent on the initial ice state are set. Some of these parameters will be described in more detail in the [Table of Namelist Inputs](#).

Two namelist variables control model initialization, `ice_ic` and `restart`. Setting `ice_ic = 'default'` causes the model to run using initial values set in the code. To start from a file **filename**, set `restart = .true.` and `ice_ic = filename`. When restarting using the Icepack driver, for simplicity the tracers are assumed to be set the same way (on/off) as in the run that created the restart file; i.e. that the restart file contains exactly the information needed for the new run. CICE is more flexible in this regard.

For stand-alone runs, routines in **icedrv_forcing.F90** read and interpolate data from files, and are intended merely for testing, although they can also provide guidance for the user to write his or her own routines.

3.1.4 Choosing an appropriate time step

Transport in thickness space imposes a restraint on the time step, given by the ice growth/melt rate and the smallest range of thickness among the categories, $\Delta t < \min(\Delta H)/2 \max(f)$, where ΔH is the distance between category boundaries and f is the thermodynamic growth rate. For the 5-category ice thickness distribution used as the default in this distribution, this is not a stringent limitation: $\Delta t < 19.4$ hr, assuming $\max(f) = 40$ cm/day.

3.1.5 Model output

History output from Icepack is not currently supported in the Icepack driver, except in restart files. The sea ice model **CICE** provides extensive options for model output, including many derived output variables.

Diagnostic files

Icepack writes diagnostic information for each grid cell as a separate file, **ice_diag.***, identified by the initial ice state of the grid cell (no ice, slab, land, etc).

Restart files

Icepack provides restart data in binary unformatted format. The restart files created by the Icepack driver contain all of the variables needed for a full, exact restart. The filename begins with the character string 'iced.' and is placed in the directory specified by the namelist variable `restart_dir`. The restart dump frequency is given by the namelist variable `dumpfreq`. The namelist variable `ice_ic` contains the pointer to the filename from which the restart data is to be read and the namelist option `restart` must be set to `.true.` to use the file.

Biogeochemistry History Fields

History output is not provided with Icepack. This documentation indicates what is available for output and is implemented in CICE.

Table *Biogeochemical History variables* lists the biogeochemical tracer history flags along with a short description and the variable or variables saved. Not listed are flags appended with `_ai`, i.e. `f_fbio_ai`. These fields are identical to their counterpart, i.e. `f_fbio`, except they are averaged by ice area.

Table 3.1: *Biogeochemical History variables*

History Flag	Definition	Variable(s)	Units
<code>f_faero_atm</code>	atmospheric aerosol deposition flux	<code>faero_atm</code>	$\text{kg m}^{-2} \text{s}^{-1}$
<code>f_faero_ocn</code>	aerosol flux from ice to ocean	<code>faero_ocn</code>	$\text{kg m}^{-2} \text{s}^{-1}$
<code>f_aero</code>	aerosol mass (snow and ice ssl and int)	<code>aerosnssl</code> , <code>aeros-noint</code> , <code>aeroicessl</code> , <code>aeroiceint</code>	kg/kg
<code>f_fbio</code>	biological ice to ocean flux	<code>fN</code> , <code>fDOC</code> , <code>fNit</code> , <code>fAm</code> , <code>fDON</code> , <code>fFep^a</code> , <code>fFed^a</code> , <code>fSil</code> , <code>fhum</code> , <code>fPON</code> , <code>fDM-SPd</code> , <code>fDMS</code> , <code>fDMSPp</code> , <code>fzaero</code>	$\text{mmol m}^{-2} \text{s}^{-1}$
<code>f_zaero</code>	bulk z-aerosol mass fraction	<code>zaero</code>	kg/kg
<code>f_bgc_S</code>	bulk z-salinity	<code>bgc_S</code>	ppt
<code>f_bgc_N</code>	bulk algal N concentration	<code>bgc_N</code>	mmol m^{-3}
<code>f_bgc_C</code>	bulk algal C concentration	<code>bgc_C</code>	mmol m^{-3}
<code>f_bgc_DOC</code>	bulk DOC concentration	<code>bgc_DOC</code>	mmol m^{-3}
<code>f_bgc_DON</code>	bulk DON concentration	<code>bgc_DON</code>	mmol m^{-3}
<code>f_bgc_DIC</code>	bulk DIC concentration	<code>bgc_DIC</code>	mmol m^{-3}
<code>f_bgc_chl</code>	bulk algal chlorophyll concentration	<code>bgc_chl</code>	mg chl m^{-3}
<code>f_bgc_Nit</code>	bulk nitrate concentration	<code>bgc_Nit</code>	mmol m^{-3}
<code>f_bgc_Am</code>	bulk ammonium concentration	<code>bgc_Am</code>	mmol m^{-3}
<code>f_bgc_Sil</code>	bulk silicate concentration	<code>bgc_Sil</code>	mmol m^{-3}
<code>f_bgc_DMSPp</code>	bulk particulate DMSP concentration	<code>bgc_DMSPp</code>	mmol m^{-3}
<code>f_bgc_DMSPd</code>	bulk dissolved DMSP concentration	<code>bgc_DMSPd</code>	mmol m^{-3}
<code>f_bgc_DMS</code>	bulk DMS concentration	<code>bgc_DMS</code>	mmol m^{-3}
<code>f_bgc_Fe</code>	bulk dissolved and particulate iron conc.	<code>bgc_Fed</code> , <code>bgc_Fep</code>	$\mu \text{mol m}^{-3}$
<code>f_bgc_hum</code>	bulk humic matter concentration	<code>bgc_hum</code>	mmol m^{-3}
<code>f_bgc_PON</code>	bulk passive mobile tracer conc.	<code>bgc_PON</code>	mmol m^{-3}
<code>f_upNO</code>	Total algal NO_3 uptake rate	<code>upNO</code>	$\text{mmol m}^{-2} \text{d}^{-1}$

Continued on next page

Table 3.1 – continued from previous page

History Flag	Definition	Variable(s)	Units
f_upNH	Total algal NH ₄ uptake rate	upNH	mmol m ⁻² d ⁻¹
f_bgc_ml	upper ocean tracer concentrations	ml_N, ml_DOC, ml_Nit, ml_Am, ml_DON, ml_Fep ^b , ml_Fed ^b , ml_Sil, ml_hum, ml_PON, ml_DMS, ml_DMSPd, ml_DMSPp	mmol m ⁻³
f_bTin	ice temperature on the bio grid	bTizn	°C
f_bphi	ice porosity on the bio grid	bphizn	%
f_iDin	brine eddy diffusivity on the interface bio grid	iDin	m ² d ⁻¹
f_iki	ice permeability on the interface bio grid	ikin	mm ²
f_fbri	ratio of brine tracer height to ice thickness	fbrine	1
f_hbri	brine tracer height	hbrine	m
f_zfswin	internal ice PAR on the interface bio grid	zfswin	W m ⁻²
f_bionet	brine height integrated tracer concentration	algalN_net, algalC_net, chl_net, pFe ^c _net, dFe ^c _net, Sil_net, Nit_net, Am_net, hum_net, PON_net, DMS_net, DMSPd_net, DMSPp_net, DOC_net, zaero_net, DON_net	mmol m ⁻²
f_biosnow	snow integrated tracer concentration	algalN_snow, algalC_snow, chl_snow, pFe ^c _snow, dFe ^c _snow, Sil_snow, Nit_snow, Am_snow, hum_snow, PON_snow, DMS_snow, DMSPd_snow, DMSPp_snow, DOC_snow, zaero_snow, DON_snow	mmol m ⁻²
f_grownet	Net specific algal growth rate	grow_net	m d ⁻¹
f_PPnet	Net primary production	PP_net	mgC m ⁻² d ⁻¹
f_algalpeak	interface bio grid level of peak chla	peak_loc	1
f_zbgc_frac	mobile fraction of tracer	algalN_frac, chl_frac, pFe_frac, dFe_frac, Sil_frac, Nit_frac, Am_frac, hum_frac, PON_frac, DMS_frac, DMSPd_frac, DMSPp_frac, DOC_frac, zaero_frac, DON_frac	1

^a units are $\mu\text{mol m}^{-2} \text{s}^{-1}$ ^b units are $\mu\text{mol m}^{-3}$ ^c units are $\mu\text{mol m}^{-2}$

3.2 Running Icepack

Quick-start instructions are provided in the [Quick Start](#) section.

3.2.1 Scripts

The icepack scripts are written to allow quick setup of cases and tests. Once a case is generated, users can manually modify the namelist and other files to custom configure the case. Several settings are available via scripts as well.

Overview

Most of the scripts that configure, build and run Icepack are contained in the directory **configuration/scripts/**, except for **icepack.setup**, which is in the main directory. **icepack.setup** is the main script that generates a case.

Users may need to port the scripts to their local machine. Specific instructions for porting are provided in [Porting](#).

`icepack.setup -h` will provide the latest information about how to use the tool. `icepack.setup --help` will provide an extended version of the help. There are three usage modes,

- `--case` or `-c` creates individual stand alone cases.
- `--test` creates individual tests. Tests are just cases that have some extra automation in order to carry out particular tests such as exact restart.
- `--suite` creates a test suite. Test suites are predefined sets of tests and `--suite` provides the ability to quick setup, build, and run a full suite of tests.

All modes will require use of `--mach` or `-m` to specify the machine and case and test modes can use `--set` or `-s` to define specific options. `--test` and `--suite` will require `--testid` to be set and both of the test modes can use `--bdir`, `--bgen`, `--bcmp`, and `--diff` to generate (save) results and compare results with prior results. Testing will be described in greater detail in the [Testing Icepack](#) section.

Again, `icepack.setup --help` will show the latest usage information including the available `--set` options, the current ported machines, and the test choices.

To create a case, run **icepack.setup**:

```
icepack.setup -c mycase -m machine
cd mycase
```

Once a case/test is created, several files are placed in the case directory

- **env.[machine]** defines the environment
- **icepack.settings** defines many variables associated with building and running the model
- **makdep.c** is a tool that will automatically generate the make dependencies
- **Macros.[machine]** defines the Makefile macros
- **Makefile** is the makefile used to build the model
- **icepack.build** is a script that builds and compiles the model
- **icepack_in** is the namelist input file
- **icepack.run** is a batch run script
- **icepack.submit** is a simple script that submits the icepack.run script

All scripts and namelist are fully resolved in the case. Users can edit any of the files in the case directory manually to change the model configuration, build options, or batch settings. The file dependency is indicated in the above list. For instance, if any of the files before **icepack.build** in the list are edited, **icepack.build** should be rerun.

The **casescripts/** directory holds scripts used to create the case and can largely be ignored. Once a case is created, the **icepack.build** script should be run interactively and then the case should be submitted by executing the

icepack.submit script interactively. The **icepack.submit** script simply submits the **icepack.run** script. You can also submit the **icepack.run** script on the command line.

Some hints:

- To change namelist, manually edit the **icepack_in** file
- To change batch settings, manually edit the top of the **icepack.run** or **icepack.test** (if running a test) file
- To turn on the debug compiler flags, set **ICE_BLDDEBUG** in **icepack.settings** to true
- To change compiler options, manually edit the Macros file
- To clean the build before each compile, set **ICE_CLEANBUILD** in **icepack.settings** to true. To not clean before the build, set **ICE_CLEANBUILD** in **icepack.settings** to false

To build and run:

```
./icepack.build
./icepack.submit
```

The build and run log files will be copied into the logs directory in the case directory. Other model output will be in the run directory. The run directory is set in **icepack.settings** via the **ICE_RUNDIR** variable. To modify the case setup, changes should be made in the case directory, NOT the run directory.

Command Line Options

icepack.setup -h provides a summary of the command line options. There are three different modes, **--case**, **--test**, and **--suite**. This section provides details about the relevant options for setting up cases with examples. Testing will be described in greater detail in the [Testing Icepack](#) section.

--help, -h prints **icepack.setup** help information to the terminal and exits.

--version prints the Icepack version to the terminal and exits.

--case, -c CASE specifies the case name. This can be either a relative path or an absolute path. This cannot be used with **--test** or **--suite**. Either **--case**, **--test**, or **--suite** is required.

--mach, -m MACHINE specifies the machine name. This should be consistent with the name defined in the Macros and env files in **configurations/scripts/machines**. This is required in all modes.

--env, -e ENVIRONMENT1,ENVIRONMENT2,ENVIRONMENT3 specifies the environment or compiler associated with the machine. This should be consistent with the name defined in the Macros and env files in **configurations/scripts/machines**. Each machine can have multiple supported environments including support for different compilers or other system setups. When used with **--suite** or **--test**, the ENVIRONMENT can be a set of comma delimited values with no spaces and the tests will then be run for all of those environments. With **--case**, only one ENVIRONMENT should be specified. (default is intel)

--pes, -p MxN specifies the number of tasks and threads the case should be run on. This only works with **--case**. The format is tasks x threads or "M"x"N" where M is tasks and N is threads and both are integers. The current icepack driver is purely serial so setting multiple tasks or multiple threads will have no impact. (default is 1x1)

--acct ACCOUNT specifies a batch account number. This is optional. See [Machine Account Settings](#) for more information.

--grid, -g GRID specifies the grid. This is a string and for the current icepack driver, only col is supported. (default = col)

--set, -s SET1,SET2,SET3 specifies the optional settings for the case. This is only used with **--case** or **--test**. The settings for **--suite** are defined in the suite file. Multiple settings can be specified by providing a comma delimited set of values without spaces between settings. The available settings are in **config-**

urations/scripts/options and `icepack.setup --help` will also list them. These settings files can change either the namelist values or overall case settings (such as the debug flag).

For Icepack, when setting up cases, the `--case` and `--mach` must be specified. It's also recommended that `--env` be set explicitly as well. At the present time, `--pes` and `--grid` cannot vary from 1x1 and col respectively which are the defaults. `--acct` is not normally used. A more convenient method is to use the `~/cice_proj` file, see [Machine Account Settings](#). The `--set` option can be extremely handy. The `--set` options are documented in [Preset Options](#).

Preset Options

There are several preset options. These are hardwired in **configurations/scripts/options** and are specified for a case or test by the `--set` command line option. You can see the full list of settings by doing `icepack.setup --help`.

The default icepack namelist and icepack settings are specified in the files **configuration/scripts/icepack_in** and **configuration/scripts/icepack.settings** respectively. When picking a preset setting (option), the `set_env.setting` and `set_nml.setting` will be used to change the defaults. This is done as part of the `icepack.setup` and the modifications are resolved in the **icepack.settings** and **icepack_in** file placed in the case directory. If multiple options are chosen and then conflict, then the last option chosen takes precedent. Not all options are compatible with each other.

Some of the options are

`debug` which turns on the compiler debug flags

`short, medium, long` which change the batch time limit

`diag1` which turns on diagnostics each timestep

`leap` which turns on the leap year

`pondcesm, pondlvl, pondtopo` which turn on the various pond schemes

`run10day, run1year, etc` which specifies a run length

`swccsm3` which turns on the ccs3 shortwave and albedo computation

`thermo1` which on turns on the Bitz-Lipscomb thermodynamics model (default is mushy-layer)

`bgc*` which turns of various bgc configurations

and there are others. To add a new option, just add the appropriate file in **configuration/scripts/options**. Some of the options settings like `smoke` and `restart` are specifically geared toward setting up tests. For more information, see [Preset Case Options](#)

Examples

The simplest case is just to setup a default configurations specifying the case name, machine, and environment:

```
icepack.setup --case mycase1 --mach spirit --env intel
```

To add some optional settings, one might do:

```
icepack.setup --case mycase2 --mach spirit --env intel --set debug,diag1,run1year,  
↪pondtopo
```

Once the cases are created, users are free to modify the `icepack.settings` and `icepack_in` namelist to further modify their setup.

3.2.2 Porting

To port, an `env.[machine]_environment` and `Macros.[machine]_environment` file have to be added to the `configuration/scripts/machines/` directory and the `configuration/scripts/icepack.batch.csh` file needs to be modified. In general, the machine is specified in `icepack.setup` with `--mach` and the environment (compiler) is specified with `--env`.

- cd to `configuration/scripts/machines/`
- Copy an existing `env` and a `Macros` file to new names for your new machine
- Edit your `env` and `Macros` files
- cd .. to `configuration/scripts/`
- Edit the `icepack.batch.csh` script to add a section for your machine with batch settings and job launch settings
- Download and untar a forcing dataset to the location defined by `ICE_MACHINE_INPUTDATA` in the `env` file

In fact, this process almost certainly will require some iteration. The easiest way to carry this out is to create an initial set of changes as described above, then create a case and manually modify the `env.[machine]` file and `Macros.[machine]` file until the case can build and run. Then copy the files from the case directory back to `configuration/scripts/machines/` and update the `configuration/scripts/icepack.batch.csh` file, retest, and then add and commit the updated machine files to the repository.

Machine Account Settings

The machine account default is specified by the variable `ICE_MACHINE_ACCT` in the `env.[machine]` file. The easiest way to change a user's default is to create a file in your home directory called `.cice_proj` and add your preferred account name to the first line. There is also an option (`--acct`) in `icepack.setup` to define the account number. The order of precedent is `icepack.setup` command line option, `.cice_proj` setting, and then value in the `env.[machine]` file.

3.2.3 Forcing data

The input data space is defined on a per machine basis by the `ICE_MACHINE_INPUTDATA` variable in the `env.[machine]` file. That file space is often shared among multiple users, and it can be desirable to consider using a common file space with group read and write permissions such that a set of users can update the inputdata area as new datasets are available.

The code is currently configured to run in standalone mode on a 4-cell grid using atmospheric data, available as detailed on the [wiki](#). These data files are designed only for testing the code, not for use in production runs or as observational data. Please do not publish results based on these data sets. Module `configuration/driver/icedrv_forcing.F90` can be modified to change the forcing data.

Icepack requires near surface atmospheric data at a single point which are set in `forcing_nml` with the `atm_data_type` in the namelist (see [Table of Icepack Settings](#)). The required fields to force icepack include: downwelling long wave and shortwave radiative fluxes, latent and sensible heat fluxes, precipitation rate, and near surface potential temperature and specific humidity.

1. Climate Forecast System (CFS)

Hourly atmospheric forcing from the National Centers for Environmental Prediction's (NCEP) Climate Forecast System, version 2 (CFSv2) [44] were utilized to generate a one-year time series for Icepack testing. These data were used to create the annual cycle at a point in the Beaufort Sea (70N, 220W) for the period of January 1 00:00UTC - December 31 23:00UTC, 2015. Additional locations can be provided for both hemispheres for the period of 1999-2015 for future testing. This dataset can be used to run for several years to reach equilibrium of the annual cycle.

Atmospheric forcing fields consist of 2-m air temperature (K), specific humidity (kg/kg), 10-m wind velocity in the x and y directions (m/s), downward solar radiation (W/m^2), downward longwave radiation (W/m^2), and precipitation ($kg/m^2/s$). Icepack's boundary layer calculation is used to derive sensible and latent heat fluxes. In the namelist, set `atm_data_type = CFS` to use CFS atmospheric forcing.

2. Field campaign derived

(a) Norwegian Young Sea Ice cruise (N-ICE)

Atmospheric, oceanic, and biogeochemical forcing are available from the 2015 Norwegian Young Sea Ice Cruise (N-ICE) [8]. These data are available daily, except for incoming atmospheric radiative forcing, which are available 6-hourly. The data correspond to the Arctic Ocean north of Svalbard along the N-ICE drift track (83N, 16E to 80N, 5E) from April 24, 2015 to June 6, 2015.

Atmospheric forcing fields from [8] consist of 2-m air temperature (K), 2-m specific humidity (kg/kg), 10-m wind velocity in the x and y directions (m/s), downward solar radiation (W/m^2), and precipitation ($kg/m^2/s$). Icepack's boundary layer calculation is used to derive sensible and latent heat fluxes. In the namelist, set `atm_data_type = NICE` to use N-ICE atmospheric forcing.

Oceanic forcing fields are available from a Parallel Ocean Program (POP) 1-degree (gx1v3) simulation run 01/08/15. These fields consist of sea surface temperature (K), sea surface salinity (ppt), boundary layer depth (m), ocean velocity in the x and y direction (m/s), and deep ocean heat flux (W/m^2). In the namelist, set `ocn_data_type = NICE` to use N-ICE oceanic forcing.

Biogeochemical forcing fields are available from the World Ocean Atlas [16]. The biogeochemical fields provided are nitrate concentration ($mmol/m^3$) and silicate concentration ($mmol/m^3$). In the namelist, set `bgc_data_type = NICE` to use N-ICE biogeochemical forcing.

(a) Ice Station Polarstern (ISPOL)

Atmospheric, oceanic, and biogeochemical forcing are available from the 2004 Ice Station Polarstern (ISPOL) [24]. These data can be used with both [6] and mushy layer thermodynamics. These data are available daily, except for incoming atmospheric radiative forcing, which are available 6-hourly. The data correspond to the Weddell Sea (67.9S, 54W) from June 16, 2004 to December 31, 2004.

Atmospheric forcing fields from [24] consist of 2-m air temperature (K), 2-m specific humidity (kg/kg), 10-m wind velocity in the x and y directions (m/s), downward solar radiation (W/m^2), and precipitation ($kg/m^2/s$). Icepack's boundary layer calculation is used to derive sensible and latent heat fluxes. In the namelist, set `atm_data_type = ISPOL` to use ISPOL atmospheric forcing.

Oceanic forcing fields are available from [24] derived from a POP 1-degree (gx1v3 simulation). These consist of sea surface temperature (K), sea surface salinity (ppt), boundary layer depth (m), ocean velocity in the x and y direction (m/s), and deep ocean heat flux (W/m^2). In the namelist, set `ocn_data_type = ISPOL` to use ISPOL oceanic forcing.

Biogeochemical forcing fields are available from the World Ocean Atlas [16]. The biogeochemical fields provided are nitrate concentration ($mmol/m^3$) and silicate concentration ($mmol/m^3$). In the namelist, set `bgc_data_type = ISPOL` to use ISPOL biogeochemical forcing.

(a) Surface HEat Budget of the Arctic (SHEBA)

The ice opening and closing rates (1/s) are derived from the SHEBA data and have been used previously in Cecilia Bitz's column model. For additional information see the following websites:

- https://atmos.washington.edu/~bitz/column_model/
- https://atmos.washington.edu/~bitz/column_model/notes_forcing_data

At present, only the opening and closing rates (1/s) are used from the forcing data. In the namelist, set `ocn_data_type = SHEBA` to use this forcing in Icepack.

3. Climatological - Maykut and Untersteiner 1971 [38]

The climatological forcing consists of a monthly climatology of downward radiative fluxes, air temperature, relative humidity and wind speed compiled from Arctic ice station observations shown in Table 1 from [29]. Icepack’s boundary layer calculation is used to derive sensible and latent heat fluxes. The snowfall follows the idealized specification used by [46]. To adjust the ice thickness a fixed heating of 6 W/m^2 is applied to the bottom of the ice. This may be thought of as containing about 2 W/m^2 of ocean heating and an adjustment of about 4 W/m^2 for biases in the forcings or the model. In the namelist, set `atm_data_type = clim` to use climatological atmospheric forcing.

3.2.4 Run Directories

The **icepack.setup** script creates a case directory. However, the model is actually built and run under the `ICE_OBJDIR` and `ICE_RUNDIR` directories as defined in the **icepack.settings** file.

Build and run logs will be copied from the run directory into the case **logs/** directory when complete.

3.2.5 Local modifications

Scripts and other case settings can be changed manually in the case directory and used. Source code can be modified in the main sandbox. When changes are made, the code should be rebuilt before being resubmitted. It is always recommended that users modify the scripts and input settings in the case directory, NOT the run directory. In general, files in the run directory are overwritten by versions in the case directory when the model is built, submitted, and run.

3.3 Testing Icepack

This section documents primarily how to use the Icepack scripts to carry out icepack testing. Exactly what to test is a separate question and depends on the kinds of code changes being made. Prior to merging changes to the CICE Consortium master, changes will be reviewed and developers will need to provide a summary of the tests carried out.

There is a base suite of tests provided by default with Icepack and this may be a good starting point for testing.

The testing scripts support several features

- Ability to test individual (via `--test`) or multiple tests (via `--suite`) using an input file to define the suite
- Ability to use test suite defined in the package or test suites defined by the user
- Ability to store test results for regression testing (`--bgen`)
- Ability to compare results to prior baselines to verify bit-for-bit (`--bcmp`)
- Ability to define where baseline tests are stored
- Ability to compare tests against each other (`--diff`)

3.3.1 Individual Tests

The Icepack scripts support both setup of individual tests as well as test suites. Individual tests are run from the command line:

```
./icepack.setup --test smoke --mach conrad --env cray --set diag1,debug --testid myid
```

Tests are just like cases but have some additional scripting around them. Individual tests can be created and manually modified just like cases. Many of the command line arguments for individual tests are similar to *Command Line Options* for `--case`. For individual tests, the following command line options can be set

--test TESTNAME specifies the test type. This is probably either smoke or restart but see *icepack.setup -help* for the latest. This is required instead of **--case**.

--testid ID specifies the testid. This is required for every use of **--test** and **--suite**. This is a user defined string that will allow each test to have a unique case and run directory name. This is also required.

--mach MACHINE (see *Command Line Options*)

--env ENVIRONMENT1 (see *Command Line Options*)

--set SET1,SET2,SET3 (see *Command Line Options*)

--acct ACCOUNT (see *Command Line Options*)

--grid GRID (see *Command Line Options*)

--pes MxN (see *Command Line Options*)

Like **--case**, **--grid** and **--pes** are not particularly useful right now within Icepack since the model can only run serially and only with the col grid setting. There are several additional options that come with **--test** that are not available with **--case** for regression and comparison testing,

--bdir DIR specifies the top level location of the baseline results. This is used in conjunction with **--bgen** and **--bcmp**. The default is set by ICE_MACHINE_BASELINE in the env.[machine]_[environment] file.

--bgen DIR specifies the name of the directory under [bdir] where test results will be stored. When this flag is set, it automatically creates that directory and stores results from the test under that directory. If DIR is set to `default`, then the scripts will automatically generate a directory name based on the Icepack hash and the date and time. This can be useful for tracking the baselines by hash.

--bcmp DIR specifies the name of the directory under [bdir] that the current tests will be compared to. When this flag is set, it automatically invokes regression testing and compares results from the current test to those prior results. If DIR is set to `default`, then the script will automatically generate the last directory name in the [bdir] directory. This can be useful for automated regression testing.

--diff LONG_TESTNAME invokes a comparison against another local test. This allows different tests to be compared to each other. The restrictions are that the test has to already be completed and the testid has to match.

The format of the case directory name for a test will always be [machine]_[env]_[test]_[grid]_[pes]_[sets].[testid] The [sets] will always be sorted alphabetically by the script so **--set debug,diag1** and **--set diag1,debug** produces the same testname and test with `_debug_diag1` in that order.

To build and run a test, the process is the same as a case. `cd` to the test directory, run the build script, and run the submit script:

```
cd [test_case]
./icepack.build
./icepack.submit
```

The test results will be generated in a local file called **test_output**. To check those results:

```
cat test_output
```

Tests are defined under **configuration/scripts/tests/**. The tests currently supported are:

- **smoke - Runs the model for default length. The length and options can** be set with the **--set** command line option. The test passes if the model completes successfully.
- **restart - Runs the model for 14 months, writing a restart file at month 3 and** again at the end of the run. Runs the model a second time starting from the month 3 restart and writing a restart at month 12 of the model run. The test passes if both runs complete and if the restart files at month 12 from both runs are bit-for-bit identical.

Please run `./icepack.setup --help` for the latest information.

Example. Basic default single test

Define the test, mach, env, and testid.

```
./icepack.setup --test smoke --mach wolf --env gnu --testid t00
cd wolf_gnu_smoke_col_1x1.t00
./icepack.build
./icepack.submit
./cat test_output
```

Example. Simple test with some options

Add `--set`

```
./icepack.setup --test smoke --mach wolf --env gnu --set diag1,debug --testid t00
cd wolf_gnu_smoke_col_1x1_debug_diag1.t00
./icepack.build
./icepack.submit
./cat test_output
```

Example. Single test, generate a baseline dataset

Add `--bgen`

```
./icepack.setup --test smoke --mach wolf --env gnu --bgen icepack.v01 --testid t00 --
↪set diag1
cd wolf_gnu_smoke_col_1x1_diag1.t00
./icepack.build
./icepack.submit
./cat test_output
```

Example. Single test, compare results to a prior baseline.

Add `--bcmp`. For this to work, the prior baseline must exist and have the exact same base testname [machine]_[env]_[test]_[grid]_[pes]_[sets]

```
./icepack.setup --test smoke --mach wolf --env gnu --bcmp icepack.v01 --testid t01 --
↪set diag1
cd wolf_gnu_smoke_col_1x1_diag1.t01
./icepack.build
./icepack.submit
./cat test_output
```

Example. Simple test, generate a baseline dataset and compare to a prior baseline

Use `--bgen` and `--bcmp`. The prior baseline must exist already.


```
./icepack.setup --test smoke --mach wolf -env gnu --bgen icepack.v02 --bcmp icepack.
↪v01 --testid t02 --set diag1
cd wolf_gnu_smoke_col_1x1_diag1.t02
./icepack.build
./icepack.submit
./cat test_output
```

Example. Simple test, comparison against another test

Use `--diff`. This feature is primarily used in test suites and has limited use in icepack, but is being described for completeness.

`--diff` provides a way to compare tests with each other. For this to work, the tests have to be run in a specific order and the testids need to match. The test is always compared relative to the current case directory.

To run the first test,

```
./icepack.setup --test smoke --mach wolf -env gnu --testid tx01 --set debug
cd wolf_gnu_smoke_col_1x1_debug.tx01
./icepack.build
./icepack.submit
./cat test_output
```

Then to run the second test and compare to the results from the first test

```
./icepack.setup --test smoke --mach wolf -env gnu --testid tx01 --diff smoke_col_1x1_
↪debug
cd wolf_gnu_smoke_col_1x1.tx01
./icepack.build
./icepack.submit
./cat test_output
```

The scripts will add a `[machine]_[environment]` to the beginning of the diff argument and the same testid to the end of the diff argument. Then the runs will be compared for bit-for-bit and a result will be produced in `test_output`. This is really more useful in CICE and for test suites right now. For example, CICE uses this feature to compare results from different pe counts or decompositions, single threaded vs multi-threaded, and so forth.

3.3.2 Test suites

Test suites support running multiple tests specified via an input file. When invoking the test suite option (`--suite`) with **icepack.setup**, all tests will be created, built, and submitted automatically under a directory called `[suite_name].[testid]` as part of invoking the suite. Because the tests are built and submitted automatically, this feature does not allow for customization of cases or tests like individual cases and tests do:

```
./icepack.setup --suite base_suite --mach wolf --env gnu --testid myid
```

Like an individual test, the `--testid` option must be specified and can be any string. Once the tests are complete, results can be checked by running the `results.csh` script in the `[suite_name].[testid]`:

```
cd base_suite.[testid]
./results.csh
```

The predefined test suites are defined under **configuration/scripts/tests** and the files defining the suites have a suffix of `.ts` in that directory. The format for the test suite file is relatively simple. It is a text file with white space delimited columns that define a handful of values in a specific order. The first column is the test name, the second the grid,

the third the pe count, the fourth column is the `--set` options and the fifth column is the `--diff` argument. (The grid and PEs columns are provided for compatibility with the similar CICE scripts.) The fourth and fifth columns are optional. Lines that begin with `#` or are blank are ignored. For example,

#Test	Grid	PEs	Sets	Diff
smoke	col	1x1	diag1	
smoke	col	1x1	diag1,runlyear	smoke_col_1x1_diag1
smoke	col	1x1	debug,runlyear	
restart	col	1x1	debug	
restart	col	1x1	diag1	
restart	col	1x1	pondcesm	
restart	col	1x1	pondlvl	
restart	col	1x1	pondtopo	

The argument to `--suite` defines the test suite (.ts) filename and that argument can contain a path. **icepack.setup** will look for the filename in the local directory, in **configuration/scripts/tests/**, or in the path defined by the `--suite` option.

Because many of the command line options are specified in the input file, **ONLY** the following options are valid for suites,

--suite filename required, input filename with list of suites

--mach MACHINE required

--env ENVIRONMENT1,ENVIRONMENT2 strongly recommended

--acct ACCOUNT optional

--testid ID required

--bdir DIR optional, top level baselines directory and defined by default by ICE_MACHINE_BASELINE in `env.[machine]_[environment]`.

--bgen DIR recommended, test output is copied to this directory under [bdir]

--bcmp DIR recommended, test output are compared to prior results in this directory under [bdir]

--report This is only used by `--suite` and when set, invokes a script that sends the test results to the results page when all tests are complete. Please see [Test Reporting](#) for more information.

Please see [Command Line Options](#) and [Individual Tests](#) for more details about how these options are used.

Example. Basic test suite

Specify suite, mach, env, testid.

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a
cd base_suite.v01a
#wait for runs to complete
./results.csh
```

Example. Basic test suite on multiple environments

Specify multiple envs.

```
./icepack.setup --suite base_suite --mach conrad --env cray,pgi,intel,gnu --testid_
↪v01a
cd base_suite.v01a
```

```
#wait for runs to complete
./results.csh
```

Each env can be run as a separate invocation of *icepack.setup* but if that approach is taken, it is recommended that different testids be used.

Example. Basic test suite, store baselines in user defined name

Add --bgen

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a --bgen_
↪icepack.v01a
cd base_suite.v01a
#wait for runs to complete
./results.csh
```

This will store the results in the default [bdir] directory under the subdirectory icepack.v01a.

Example. Basic test suite, store baselines in user defined top level directory

Add --bgen and --bdir

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a --bgen_
↪icepack.v01a --bdir /tmp/user/ICEPACK_BASELINES
cd base_suite.v01a
#wait for runs to complete
./results.csh
```

This will store the results in /tmp/user/ICEPACK_BASELINES/icepack.v01a.

Example. Basic test suite, store baselines in auto-generated directory

Add --bgen default

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a --bgen_
↪default
cd base_suite.v01a
#wait for runs to complete
./results.csh
```

This will store the results in the default [bdir] directory under a directory name generated by the script that includes the hash and date.

Example. Basic test suite, compare to prior baselines

Add --bcmp

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v02a --bcmp_
↪icepack.v01a
cd base_suite.v02a
#wait for runs to complete
./results.csh
```

This will compare to results saved in the baseline [bdir] directory under the subdirectory icepack.v01a. You can use other regression options as well (`--bdir` and `--bgen`)

Example. Basic test suite, use of default string in regression testing

default is a special argument to `--bgen` and `--bcmp`. When used, the scripts will automate generation of the directories. In the case of `--bgen`, a unique directory name consisting of the hash and a date will be created. In the case of `--bcmp`, the latest directory in [bdir] will automatically be specified. This provides a number of useful features

- the `--bgen` directory will be named after the hash automatically
- the `--bcmp` will always find the most recent set of baselines
- the `--bcmp` reporting will include information about the comparison directory name which will include hash information
- automation can be invoked easily, especially if `--bdir` is used to separate results

Imagine the case where the default settings are used and `--bdir` is used to create a unique location. You could easily carry out regular builds automatically via,

```
set mydate = `date -u "+%Y%m%d"`
git clone https://github.com/myfork/icepack icepack.$mydate
cd icepack.$mydate
./icepack.setup --suite base_suite --mach conrad --env cray,gnu,intel,pgi --testid
↪$mydate --bcmp default --bgen default --bdir /tmp/work/user/ICEPACK_BASELINES_MASTER
```

When this is invoked, a new set of baselines will be generated and compared to the prior results each time without having to change the arguments.

Example. Create and test a custom suite

Create your own input text file consisting of 5 columns of data,

- Test
- Grid
- pes
- sets (optional)
- diff test (optional)

such as

```
> cat mysuite
smoke    col    1x1    diag1,debug
restart  col    1x1
restart  col    1x1    diag1,debug    restart_col_1x1
restart  col    1x1    mynewoption,diag1,debug
```

then use that input file, mysuite

```
./icepack.setup --suite mysuite --mach conrad --env cray --testid v01a --bgen default
cd mysuite.v01a
#wait for runs to complete
./results.csh
```

You can use all the standard regression testing options (`--bgen`, `--bcmp`, `--bdir`). Make sure any “diff” testing that goes on is on tests that are created earlier in the test list, as early as possible. Unfortunately, there is still no absolute guarantee the tests will be completed in the correct sequence.

3.3.3 Test Reporting

The Icepack testing scripts have the capability to post test results to the official [wiki page](#). You may need write permission on the wiki. If you are interested in using the wiki, please contact the consortium.

To post results, once a test suite is complete, run `results.csh` and `report_results.csh` from the suite directory,

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a
cd base_suite.v01a
#wait for runs to complete
./results.csh
./report_results.csh
```

The reporting can also be automated by adding `--report`

```
./icepack.setup --suite base_suite --mach conrad --env cray --testid v01a --report
```

With `--report`, the suite will create all the tests, build and submit them, wait for all runs to be complete, and run the results and `report_results` scripts.

3.3.4 Test Plotting

The Icepack scripts include a script (`timeseries.csh`) that will generate a timeseries figure from the diagnostic output file. When running a test suite, the `timeseries.csh` script is automatically copied to the suite directory. If the `timeseries.csh` script is to be used on a test / case that is not a part of a test suite, users will need to run the `timeseries.csh` script from the tests directory (`./configuration/scripts/tests/timeseries.csh`), or copy it to a local directory and run it locally (`cp configuration/scripts/tests/timeseries.csh .` followed by `./timeseries.csh /path/to/ice_diag.full_ITD`). The plotting script can be run on any of the output files - `icefree`, `slab`, `full_ITD`, `land`). To generate the figure, run the `timeseries.csh` script and pass the full path to the `ice_diag` file as an argument.

For example:

Run the test suite.

```
$ ./icepack.setup -m conrad -e intel --suite base_suite -acct <account_number> --
↳ testid t00
```

Wait for suite to finish then go to the directory.

```
$ cd base_suite.t00
```

Run the `timeseries` script on the desired case.

```
$ ./timeseries.csh /p/work1/turner/ICEPACK_RUNS/conrad_intel_smoke_col_1x1_diag1_
↳ run1year.t00/ice_diag.full_ITD
```

The output figures are placed in the directory where the `ice_diag` file is located.

This plotting script can be used to plot the following variables:

- area fraction

- average ice thickness (m)
- average snow depth (m)
- air temperature (C)
- shortwave radiation (W/m^2)
- longwave radiation (W/m^2)
- snowfall
- average salinity (ppt)
- surface temperature (C)
- outward longwave flux (W/m^2)
- sensible heat flux (W/m^2)
- latent heat flux (W/m^2)
- top melt (m)
- bottom melt (m)
- lateral melt (m)
- new ice (m)
- congelation (m)
- snow-ice (m)
- initial energy change (W/m^2)

3.4 Case Settings

There are two important files that define the case, **icepack.settings** and **icepack.in**. **icepack.settings** is a list of env variables that define many values used to setup, build and run the case. **icepack.in** is the input namelist file for the icepack driver. Variables in both files are described below.

3.4.1 Table of Icepack Settings

The **icepack.settings** file is reasonably well self documented. Several of the variables defined in the file are not used in Icepack. They exist to support the CICE model.

Table 3.2: *Icepack settings*

variable	options/format	description	recommended value
ICE_CASENAME		case name	set by icepack.setup
ICE_SANDBOX		sandbox directory	set by icepack.setup
ICE_MACHINE		machine name	set by icepack.setup
ICE_COMPILER		environment name	set by icepack.setup
ICE_MACHCOMP		machine_environment name	set by icepack.setup
ICE_SCRIPTS		scripts directory	set by icepack.setup
ICE_CASEDIR		case directory	set by icepack.setup
ICE_RUNDIR		run directory	set by icepack.setup
ICE_OBJDIR		compile directory	\${ICE_RUNDIR}/compile

Continued on next page

Table 3.2 – continued from previous page

variable	options/format	description	recommended value
ICE_RSTDIR		unused	\${ICE_RUNDIR}/restart
ICE_HSTDIR		unused	\${ICE_RUNDIR}/history
ICE_LOGDIR		log directory	\${ICE_CASEDIR}/logs
ICE_RSTPFILE		unused	undefined
ICE_DRVOPT		unused	icepack
ICE_CONSTOPT		unused	cice
ICE_IOTYPE		unused	none
ICE_CLEANBUILD	true,false	automatically clean before building	true
ICE_GRID	col	grid	col
ICE_NXGLOB	4	number of gridcells	4
ICE_NTASKS	1	number of tasks, must be set to 1	1
ICE_NTHRDS	1	number of threads per task, must be set to 1	1
ICE_TEST		test setting if using a test	set by icepack.setup
ICE_TESTNAME		test name if using a test	set by icepack.setup
ICE_BASELINE		baseline directory name, associated with icepack.setup -bd	set by icepack.setup
ICE_BASEGEN		baseline directory name for regression generation, associated with icepack.setup -bg	set by icepack.setup
ICE_BASECOM		baseline directory name for regression comparison, associated with icepack.setup -bc	set by icepack.setup
ICE_BFBCOMP		location of case for comparison, associated with icepack.setup -td	set by icepack.setup
ICE_SPVAL		unused	UnDeFiNeD
ICE_RUNLENGTH		batch run length default	00:10:00
ICE_ACCOUNT		batch account number	set by icepack.setup or by default
ICE_THREADED	true,false	force threading in compile, will always compile threaded if NTHRDS is gt 1	false
NICELYR		number of vertical layers in the ice	7
NSNWLYR		number of vertical layers in the snow	1
NICECAT		number of ice thickness categories	5
TRAGE	0,1	ice age tracer	1
TRFY	0,1	first-year ice area tracer	1
TRLVL	0,1	deformed ice tracer	1
TRPND	0,1	melt pond tracer	1
NTRAERO		number of aerosol tracers	1
TRBRI	0,1	brine height tracer	0
TRZS	0,1	zsalinity tracer, needs TRBRI=1	0
TRBGCS	0,1	skeletal layer tracer, needs TRBGCZ=0	0
TRBGCZ	0,1	zbgc tracers, needs TRBGCS=0 and TRBRI=1	0
NBGCLYR		number of zbgc layers	7

Continued on next page

Table 3.2 – continued from previous page

variable	options/format	description	recommended value
TRZAERO	0-6	number of z aerosol tracers	0
TRALG	0,1,2,3	number of algal tracers	0
TRDOC	0,1,2,3	number of dissolved organic carbon	0
TRDIC	0,1	number of dissolved inorganic carbon	0
TRDON	0,1	number of dissolved organic nitrogen	0
TRFEP	0,1,2	number of particulate iron tracers	0
TRFED	0,1,2	number of dissolved iron tracers	0
CAM_ICE		unused	no
DITTO		unused	no
BARRIERS		unused	no
ICE_BLDDEBUG	true,false	turn on compile debug flags	false
NUMIN		unused	11
NUMAX		unused	99

3.4.2 Table of Namelist Inputs

Namelist is part of the icepack driver code and is used to setup testing of the column physics.

Table 3.3: *Namelist Inputs*

variable	options/format	description	recommended value
<i>setup_nml</i>			
		<i>Time, Diagnostics</i>	
days_per_year	360 or 365	number of days in a model year	365
use_leap_years	true/false	if true, include leap days	
year_init	yyyy	the initial year, if not using restart	
istep0	integer	initial time step number	0
dt	seconds	thermodynamics time step length	3600.
npt	integer	total number of time steps to take	
ndtd	integer	number of dynamics/advection/ridging/steps per thermo timestep	1
		<i>Initialization/Restarting</i>	
ice_ic	default	latitude and sst dependent	default
	none	no ice	
	path/file	restart file name	
restart_dir	path/	path to restart directory	
dumpfreq	y	write restart every dumpfreq_n years	y
	m	write restart every dumpfreq_n months	
	d	write restart every dumpfreq_n days	
		<i>Model Output</i>	
diagfreq	integer	frequency of diagnostic output in dt	24
	e.g., 10	once every 10 time steps	
diag_file	filename	diagnostic output file (script may reset)	

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
<i>grid_nml</i>			
		<i>Grid</i>	
kcatbound	0	original category boundary formula	0
	1	new formula with round numbers	
	2	WMO standard categories	
	-1	one category	
<i>tracer_nml</i>			
		<i>Tracers</i>	
tr_iage	true/false	ice age	
tr_FY	true/false	first-year ice area	
tr_lvl	true/false	level ice area and volume	
tr_pond_cesm	true/false	CESM melt ponds	
tr_pond_topo	true/false	topo melt ponds	
tr_pond_lvl	true/false	level-ice melt ponds	
tr_aero	true/false	aerosols	
<i>thermo_nml</i>			
		<i>Thermodynamics</i>	
kitd	0	delta function ITD approximation	1
	1	linear remapping ITD approximation	
ktherm	0	zero-layer thermodynamic model	
	1	Bitz and Lipscomb thermodynamic model	
	2	mushy-layer thermodynamic model	
conduct	MU71	conductivity [38]	
	bubbly	conductivity [41]	
a_rapid_mode	real	brine channel diameter	0.5×10^{-3} m
Rac_rapid_mode	real	critical Rayleigh number	10
aspect_rapid_mode	real	brine convection aspect ratio	1
dSdt_slow_mode	real	drainage strength parameter	-1.5×10^{-7} m/s/K
phi_c_slow_mode	$0 < \phi_c < 1$	critical liquid fraction	0.05
phi_i_mushy	$0 < \phi_i < 1$	solid fraction at lower boundary	0.85
<i>dynamics_nml</i>			
		<i>Dynamics</i>	
kstrength	0	ice strength formulation [19]	1
	1	ice strength formulation [43]	
krdg_partic	0	old ridging participation function	1
	1	new ridging participation function	
krdg_redist	0	old ridging redistribution function	1
	1	new ridging redistribution function	
mu_rdg	real	e-folding scale of ridged ice	
Cf	real	ratio of ridging work to PE change in ridging	17.

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
<i>shortwave_nml</i>			
		<i>Shortwave</i>	
shortwave	ccsm3	NCAR CCSM3 distribution method	‘dEdd’
	dEdd	Delta-Eddington method	
albedo_type	ccsm3	NCAR CCSM3 albedos	‘ccsm3’
	constant	four constant albedos	
albicev	$0 < \alpha < 1$	visible ice albedo for thicker ice	
albicev	$0 < \alpha < 1$	near infrared ice albedo for thicker ice	
albsnowv	$0 < \alpha < 1$	visible, cold snow albedo	
albsnowi	$0 < \alpha < 1$	near infrared, cold snow albedo	
ahmax	real	albedo is constant above this thickness	0.3 m
R_ice	real	tuning parameter for sea ice albedo from Delta-Eddington shortwave	
R_pnd	real	... for ponded sea ice albedo ...	
R_snw	real	... for snow (broadband albedo) ...	
dT_mlt	real	Δ temperature per Δ snow grain radius	
rsnw_mlt	real	maximum melting snow grain radius	
kalg	real	absorption coefficient for algae	
<i>ponds_nml</i>			
		<i>Melt Ponds</i>	
hpl	real	critical ice lid thickness for topo ponds	0.01 m
hs0	real	snow depth of transition to bare sea ice	0.03 m
hs1	real	snow depth of transition to pond ice	0.03 m
dpscale	real	time scale for flushing in permeable ice	1×10^{-3}
frzpond	hlid	Stefan refreezing with pond ice thickness	‘hlid’
	cesm	CESM refreezing empirical formula	
rfracmin	$0 \leq r_{min} \leq 1$	minimum melt water added to ponds	0.15
rfracmax	$0 \leq r_{max} \leq 1$	maximum melt water added to ponds	1.0
pndaspect	real	aspect ratio of pond changes (depth:area)	0.8
<i>forcing_nml</i>			
		<i>Forcing</i>	
formdrag	true/false	calculate form drag	
atmbndy	default	stability-based boundary layer	‘default’
	constant	bulk transfer coefficients	
fyear_init	yyyy	first year of atmospheric forcing data	
ycycle	integer	number of years in forcing data cycle	
atm_data_type	default	constant values defined in the code	
	clim	monthly climatology (see <i>Forcing data</i>)	
	CFS	CFS model output (see <i>Forcing data</i>)	
	ISPOL	ISPOL experiment data (see <i>Forcing data</i>)	
	NICE	N-ICE experiment data (see <i>Forcing data</i>)	
data_dir	path/	path to forcing data directory	
calc_strair	true	calculate wind stress and speed	
	false	read wind stress and speed from files	
highfreq	true/false	high-frequency atmo coupling	
natmiter	integer	number of atmo boundary layer iterations	

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
calc_Tsfc	true/false	calculate surface temperature	.true.
precip_units	mks	liquid precipitation data units	
	mm_per_month		
	mm_per_sec	(same as MKS units)	
tfrz_option	minus1p8	constant ocean freezing temperature (-1.8°C)	
	linear_salt	linear function of salinity (ktherm=1)	
	mushy	matches mushy-layer thermo (ktherm=2)	
default_season	winter	Sets initial values of forcing and is overwritten when forcing read in. Default is winter	
	summer	typical summer values	
	spring	typical spring values	
ustar_min	real	minimum value of ocean friction velocity	0.0005 m/s
fbot_xfer_type	constant	constant ocean heat transfer coefficient	
	Cdn_ocn	variable ocean heat transfer coefficient	
update_ocn_f	true	include frazil water/salt fluxes in ocn fluxes	
	false	do not include (when coupling with POP)	
l_mpond_fresh	true	retain (topo) pond water until ponds drain	
	false	release (topo) pond water immediately to ocean	
oceanmixed_ice	true/false	active ocean mixed layer calculation	.true. (if uncoupled)
ocn_data_type	default	constant values defined in the code	
	ISPOL	ISPOL experiment data (see Forcing data)	
	NICE	N-ICE experiment data (see Forcing data)	
	SHEBA	Opening/closing dataset from SHEBA	
oceanmixed_file	filename	data file containing ocean forcing data	
restore_ocn	true/false	restore sst to data	
trestore	integer	sst restoring time scale (days)	
zbgc_nml			
		<i>Biogeochemistry</i>	
tr_brine	true/false	brine height tracer (needs TRBRI 1 in comp_ice)	.true.
restart_hbrine	true/false	restart the brine height tracer (automatically turned on if restart = .true.)	.false.
tr_zaero	true/false	turns on black carbon and dust aerosols	.false.
modal_aero	true/false	turns on a modal aerosol option	.false.
skl_bgc	true/false	turns on a single bottom layer biogeochemistry. z_tracers and solve_zbgc must be false	.false.
z_tracers	true/false	turns on a vertically resolved transport	.true.
dEdd_algae	true/false	Include radiative impact of algae and aerosols in the delta-Eddington shortwave scheme. Requires shortwave = 'dEdd'.	.false.

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
solve_zbgc	true/false	turns on the biochemistry using z_tracers (specify algal numbers in comp_ice TRALG)	.true.
bgc_flux_type	Jin2006 or default	ice-ocean flux type for bottom layer tracers only [26]	Jin2006
restore_bgc	true/false	restores upper ocean concentration fields to data values for nitrate and silicate	.false.
restart_bgc	true/false	restarts biogeochemical tracers (automatically turned on if restart = .true.)	.false.
scale_bgc	true/false	Initialize biogeochemical profiles to scale with prognosed salinity profile	.false.
solve_zsal	true/false	prognostic salinity tracer used with ktherm = 1	.false.
restart_zsal	true/false	restarts zsalinity	.false.
bgc_data_dir	/ nitrate_and_silicate/ forcing_directory/		‘/ nitrate_and_silicate/ forcing_directory/ ,
bgc_data_type	default	fixed, spatially homogeneous constant values defined in the code	
	clim	monthly climatology data file (see ice-driv_forcing_bgc.F90) [17]	
	NICE	NICE experiment data	
	ISPOL	ISPOL experiment data	
tr_bgc_Nit	true/false	nitrate tracer	.true.
tr_bgc_C	true/false	dissolved organic carbon tracers and dissolved inorganic carbon tracers (not yet implemented)	.true.
tr_bgc_chl	true/false	dummy variable for now. Chl is simply fixed ratio of algal Nitrogen	.false.
tr_bgc_Am	true/false	Ammonium	.true.
tr_bgc_Sil	true/false	Silicate	.true.
tr_bgc_DMS	true/false	Three tracers: DMS dimethyl sulfide, DMSPp (particulate, assumed to be a fixed ratio of sulfur to algal nitrogen) and DM-SPd (dissolved)	.true.
tr_bgc_PON	true/false	passive purely mobile ice tracer with ocean concentration equivalent to nitrate	.false.
tr_bgc_hum	true/false	refractory DOC or DON (units depend on the ocean source)	.true.
tr_bgc_DON	true/false	dissolved organic nitrogen	.true.
tr_bgc_Fe	true/false	dissolved iron and particulate iron	.true.
grid_o	real	ice-ocean surface layer thickness (bgc transport scheme)	0.006
l_sk	real	length scale in gravity drainage parameterization (bgc transport scheme)	0.024
grid_oS	real	ice-ocean surface layer thickness (zsalinity transport scheme)	0.0

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
l_skS	real	ice-atmosphere surface layer thickness (zsalinity transport scheme)	0.028
phi_snow	real	snow porosity at the ice-snow interface. if < 0 then phi_snow is computed from snow density	-0.3
initbio_frac	real	for each bgc tracer, specifies the fraction of the ocean concentration that is retained in the ice during initial new ice formation	0.8
frazil_scav	real	for each bgc tracer, specifies the fraction or multiple of the ocean concentration that is retained in the ice from frazil ice formation	0.8
ratio_si2N_diatoms	real	algal Si to N (mol/mol) for diatoms	1.8
ratio_si2N_sp	real	algal Si to N (mol/mol) for small phytoplankton	0.0
ratio_si2N_phaeo	real	algal Si to N (mol/mol) for phaeocystis	0.0
ratio_S2N_diatoms	real	algal S to N (mol/mol) for diatoms	0.03
ratio_S2N_sp	real	algal S to N (mol/mol) for small phytoplankton	0.03
ratio_S2N_phaeo	real	algal S to N (mol/mol) for phaeocystis	0.03
ratio_Fe2C_diatoms	real	algal Fe to C ($\mu mol/mol$) for diatoms	0.0033
ratio_Fe2C_sp	real	algal Fe to C ($\mu mol/mol$) for small phytoplankton	0.0033
ratio_Fe2C_phaeo	real	algal Fe to C ($\mu mol/mol$) for phaeocystis	0.1
ratio_Fe2N_diatoms	real	algal Fe to N ($\mu mol/mol$) for diatoms	0.023
ratio_Fe2N_sp	real	algal Fe to N ($\mu mol/mol$) for small phytoplankton	0.023
ratio_Fe2N_phaeo	real	algal Fe to N ($\mu mol/mol$) for phaeocystis	0.7
ratio_Fe2DON	real	Fe to N of DON ($nmol/mol$)	0.023
ratio_Fe2DOC_s	real	Fe to C of DOC for saccharids ($nmol/mol$)	0.1
ratio_Fe2DOC_l	real	Fe to C of DOC for lipids ($nmol/mol$)	0.033
fr_resp	real	fraction of algal growth lost due to respiration	0.05
tau_min	real	rapid mobile to stationary exchanges (s)	5200.0
tau_max	real	long time mobile to stationary exchanges (s)	1.73e5
algal_vel	real	0.5 $cm/day(m/s)$	1.11e-8
R_dFe2dust	real	g/g (3.5% content)	0.035
dustFe_sol	real	solubility fraction	0.005
chlabs_diatoms	real	diatoms chl absorption ($1/m/(mg/m^3)$)	0.03
chlabs_sp	real	small phytoplankton chl absorption ($1/m/(mg/m^3)$)	0.01
chlabs_phaeo	real	phaeocystis chl absorption ($1/m/(mg/m^3)$)	0.05
alpha2max_low_diatoms	real	diatoms light limitation ($(W/m^2)^{-1}$)	0.8
alpha2max_low_sp	real	small phytoplankton light limitation ($(W/m^2)^{-1}$)	0.67
alpha2max_low_phaeo	real	phaeocystis light limitation ($(W/m^2)^{-1}$)	0.67

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
beta2max_diatoms	real	diatoms light inhibition $((W/m^2)^{-1})$	0.018
beta2max_sp	real	small phytoplankton light inhibition $((W/m^2)^{-1})$	0.0025
beta2max_phaeo	real	phaeocystis light inhibition $((W/m^2)^{-1})$	0.01
mu_max_diatoms	real	diatoms maximum growth rate (day^{-1})	1.2
mu_max_sp	real	small phytoplankton maximum growth rate (day^{-1})	0.851
mu_max_phaeo	real	phaeocystis maximum growth rate (day^{-1})	0.851
grow_Tdep_diatoms	real	diatoms Temperature dependence of growth $(^{\circ}C^{-1})$	0.06
grow_Tdep_sp	real	small phytoplankton Temperature dependence of growth $^{\circ}C^{-1}$	0.06
grow_Tdep_phaeo	real	phaeocystis Temperature dependence of growth $^{\circ}C^{-1}$	0.06
fr_graze_diatoms	real	diatoms fraction grazed	0.01
fr_graze_sp	real	small phytoplankton fraction grazed	0.1
fr_graze_phaeo	real	phaeocystis fraction grazed	0.1
mort_pre_diatoms	real	diatoms mortality (day^{-1})	0.007
mort_pre_sp	real	small phytoplankton mortality (day^{-1})	0.007
mort_pre_phaeo	real	phaeocystis mortality (day^{-1})	0.007
mort_Tdep_diatoms	real	diatoms temperature dependence of mortality $^{\circ}C^{-1}$	0.03
mort_Tdep_sp	real	small phytoplankton temperature dependence of mortality $(^{\circ}C^{-1})$	0.03
mort_Tdep_phaeo	real	phaeocystis temperature dependence of mortality $(^{\circ}C^{-1})$	0.03
k_exude_diatoms	real	diatoms algal exudation (day^{-1})	0.0
k_exude_sp	real	small phytoplankton algal exudation (day^{-1})	0.0
k_exude_phaeo	real	phaeocystis algal exudation (day^{-1})	0.0
K_Nit_diatoms	real	diatoms nitrate half saturation $(mmol/m^3)$	1.0
K_Nit_sp	real	small phytoplankton nitrate half saturation $(mmol/m^3)$	1.0
K_Nit_phaeo	real	phaeocystis nitrate half saturation $(mmol/m^3)$	1.0
K_Am_diatoms	real	diatoms ammonium half saturation $(mmol/m^3)$	0.3
K_Am_sp	real	small phytoplankton ammonium half saturation $(mmol/m^3)$	0.3
K_Am_phaeo	real	phaeocystis ammonium half saturation $(mmol/m^3)$	0.3
K_Sil_diatoms	real	diatoms silicate half saturation $(mmol/m^3)$	4.0
K_Sil_sp	real	small phytoplankton silicate half saturation $(mmol/m^3)$	0.0
K_Sil_phaeo	real	phaeocystis silicate half saturation $(mmol/m^3)$	0.0
K_Fe_diatoms	real	diatoms iron half saturation (nM)	1.0

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
K_Fe_sp	real	small phytoplankton iron half saturation (nM)	0.2
K_Fe_phaeo	real	phaeocystis iron half saturation (nM)	0.1
f_don_protein	real	fraction of spilled grazing to proteins	0.6
kn_bac_protein	real	Bacterial degradation of DON (day^{-1})	0.03
f_don_Am_protein	real	fraction of remineralized DON to ammonium	0.25
f_doc_s	real	fraction of mortality to DOC saccharids	0.4
f_doc_l	real	fraction of mortality to DOC lipids	0.4
f_exude_s	real	fraction of exudation to DOC saccharids	1.0
f_exude_l	real	fraction of exudation to DOC lipids	1.0
k_bac_s	real	bacterial degradation of DOC (day^{-1}) saccharids	0.03
k_bac_l	real	bacterial degradation of DOC (day^{-1}) lipids	0.03
T_max	real	maximum temperature ($^{\circ}C$)	0.0
fsal	real	Salinity limitation (ppt)	1.0
op_dep_min	real	Light attenuates for optical depths exceeding min	0.1
fr_graze_s	real	fraction of grazing spilled or slopped	0.5
fr_graze_e	real	fraction of assimilation excreted	0.5
fr_mort2min	real	fractionation of mortality to Am	0.5
fr_dFe	real	fraction of remineralized nitrogen (algal iron)	0.3
k_nitrif	real	nitrification rate (day^{-1})	0.0
t_iron_conv	real	desorption loss pFe to dFe (day)	3065.0
max_loss	real	restrict uptake to % of remaining value	0.9
max_dfe_docl	real	max ratio of dFe to saccharides in the ice ($nMFe/\mu MC$)	0.2
fr_resp_s	real	DMSPd fraction of respiration loss as DMSPd	0.75
y_sk_DMS	real	fraction conversion given high yield	0.5
t_sk_conv	real	Stefels conversion time (day)	3.0
t_sk_ox	real	DMS oxidation time (day)	10.0
algatype_diatoms	real	mobility type between stationary <=> mobile for diatoms	0.0
algatype_sp	real	mobility type between stationary <=> mobile for small phytoplankton	0.5
algatype_phaeo	real	mobility type between stationary <=> mobile for phaeocystis	0.5
nitratetype	real	mobility type between stationary <=> mobile for nitrate	-1.0
ammoniumtype	real	mobility type between stationary <=> mobile for ammonium	1.0
silicatetype	real	mobility type between stationary <=> mobile for silicate	-1.0
dmsptype	real	mobility type between stationary <=> mobile for DMSP particulate	0.5

Continued on next page

Table 3.3 – continued from previous page

variable	options/format	description	recommended value
dmspdtype	real	mobility type between stationary <=> mobile for DMSP dissolved	-1.0
humtype	real	mobility type between stationary <=> mobile for humic matter	1.0
doctype_s	real	mobility type between stationary <=> mobile for DOC saccharids	0.5
doctype_l	real	mobility type between stationary <=> mobile for DOC lipids	0.5
dontype_protein	real	mobility type between stationary <=> mobile for proteins	0.5
fedtype_1	real	mobility type between stationary <=> mobile for FeD	0.5
feptype_1	real	mobility type between stationary <=> mobile for FeP	0.5
zaerotype_bc1	real	mobility type between stationary <=> mobile for zaerotype_bc1	1.0
zaerotype_bc2	real	mobility type between stationary <=> mobile for zaerotype_bc2	1.0
zaerotype_dust1	real	mobility type between stationary <=> mobile for dust1	1.0
zaerotype_dust2	real	mobility type between stationary <=> mobile for dust2	1.0
zaerotype_dust3	real	mobility type between stationary <=> mobile for dust3	1.0
zaerotype_dust4	real	mobility type between stationary <=> mobile for dust4	1.0
ratio_C2N_diatoms	real	diatom algal C to N ratio (<i>mol/mol</i>)	7.0
ratio_C2N_sp	real	small phytoplankton algal C to N ratio (<i>mol/mol</i>)	7.0
ratio_C2N_phaeo	real	phaeocystis algal C to N ratio (<i>mol/mol</i>)	7.0
ratio_chl2N_diatoms	real	diatom algal chlorophyll to N ratio (<i>mg/mmol</i>)	2.1
ratio_chl2N_sp	real	small phytoplankton algal chlorophyll to N ratio (<i>mg/mmol</i>)	1.1
ratio_chl2N_phaeo	real	phaeocystis algal chlorophyll to N ratio (<i>mg/mmol</i>)	0.84
F_abs_chl_diatoms	real	diatom scales absorbed radiation for dEdd	2.0
F_abs_chl_sp	real	small phytoplankton scales absorbed radiation for dEdd	4.0
F_abs_chl_phaeo	real	phaeocystis scales absorbed radiation for dEdd	5.0
ratio_C2N_proteins	real	ratio of C to N in proteins (<i>mol/mol</i>)	7.0

3.4.3 BGC Tuning Parameters

Biogeochemical tuning parameters are specified as namelist options in `icepack.in`. Table *Biogeochemical Reaction Parameters* provides a list of parameters used in the reaction equations, their representation in the code, a short description of each and the default values. Please keep in mind that there has only been minimal tuning of the model.

Table 3.4: *Biogeochemical Reaction Parameters*

Text Variable	Variable in code	Description	Value	units
f_{graze}	fr_graze(1:3)	fraction of growth grazed	0, 0.1, 0.1	1
f_{res}	fr_resp	fraction of growth respired	0.05	1
l_{max}	max_loss	maximum tracer loss fraction	0.9	1
m_{pre}	mort_pre(1:3)	maximum mortality rate	0.007, 0.007, 0.007	day ⁻¹
m_T	mort_Tdep(1:3)	mortality temperature decay	0.03, 0.03, 0.03	°C ⁻¹
T_{max}	T_max	maximum brine temperature	0	°C
k_{nitr}	k_nitrif	nitrification rate	0	day ⁻¹
f_{ng}	fr_graze_e	fraction of grazing excreted	0.5	1
f_{gs}	fr_graze_s	fraction of grazing spilled	0.5	1
f_{nm}	fr_mort2min	fraction of mortality to NH ₄	0.5	1
f_{dg}	f_don	frac. spilled grazing to DON	0.6	1
k_{nb}	kn_bac ^a	bacterial degradation of DON	0.03	day ⁻¹
f_{cg}	f_doc(1:3)	fraction of mortality to DOC	0.4, 0.4, 0.2	1
$R_{c:n}^c$	R_C2N(1:3)	algal carbon to nitrogen ratio	7.0, 7.0, 7.0	mol/mol
k_{cb}	k_bac1:3 ^a	bacterial degradation of DOC	0.03, 0.03, 0.03	day ⁻¹
τ_{fe}	t_iron_conv	conversion time pFe ↔ dFe	3065.0	day
$r_{fed:doc}^{max}$	max_dfe_doc1	max ratio of dFe to saccharids	0.1852	nM Fe/μM C
f_{fa}	fr_dFe	fraction of remin. N to dFe	0.3	1
$R_{fe:n}$	R_Fe2N(1:3)	algal Fe to N ratio	0.023, 0.023, 0.7	mmol/mol
$R_{s:n}$	R_S2N(1:3)	algal S to N ratio	0.03, 0.03, 0.03	mol/mol
f_{sr}	fr_resp_s	resp. loss as DMSPd	0.75	1
τ_{dmsp}	t_sk_conv	Stefels rate	3.0	day
τ_{dms}	t_sk_ox	DMS oxidation rate	10.0	day
y_{dms}	y_sk_DMS	yield for DMS conversion	0.5	1
K_{NO_3}	K_Nit(1:3)	NO ₃ half saturation constant	1,1,1	mmol/m ³
K_{NH_4}	K_Am(1:3)	NH ₄ half saturation constant	0.3, 0.3, 0.3	mmol/m ⁻³

Continued on next page

Table 3.4 – continued from previous page

Text Variable	Variable in code	Description	Value	units
K_{SiO_3}	K_Sil(1:3)	silicate half saturation constant	4.0, 0, 0	mmol/m ⁻³
K_{fed}	K_Fe(1:3)	iron half saturation constant	1.0, 0.2, 0.1	μmol/m ⁻³
op_{min}	op_dep_min	boundary for light attenuation	0.1	1
$chlabs$	chlabs(1:3)	light absorption length per chla conc.	0.03, 0.01, 0.05	1/m/(mg/m ³)
α	alpha2max_low(1:3)	light limitation factor	0.25, 0.25, 0.25	m ² /W
β	beta2max(1:3)	light inhibition factor	0.018, 0.0025, 0.01	m ² /W
μ_{max}	mu_max(1:3)	maximum algal growth rate	1.44, 0.851, 0.851	day ⁻¹
μ_T	grow_Tdep(1:3)	temperature growth factor	0.06, 0.06, 0.06	day ⁻¹
f_{sal}	fsal	salinity growth factor	1	1
$R_{\text{si:n}}$	R_Si2N(1:3)	algal silicate to nitrogen	1.8, 0, 0	mol/mol

^a only (1:2) of DOC and DOC parameters have physical meaning

3.5 Troubleshooting

Check the FAQ: <https://github.com/CICE-Consortium/Icepack/wiki>

3.5.1 Initial setup

If there are problems, you can manually edit the env, Macros, and **icepack.run** files in the case directory until things are working properly. Then you can copy the env and Macros files back to **configuration/scripts/machines**.

- Changes made directly in the run directory, e.g. to the namelist file, will be overwritten if scripts in the case directory are run again later.
- If changes are needed in the **icepack.run.setup.csh** script, it must be manually modified.

3.5.2 Restarts

- Manual restart tests require the path to the restart file be included in `ice_in` in the namelist file.
- Ensure that `kcatbound` is the same as that used to create the restart file. Other configuration parameters, such as `NICELYR`, must also be consistent between runs.

3.5.3 Debugging hints

Icepack has a warning package (**/columnphysics/icepack_warnings.F90**) where icepack stores information not set in write routines. Details about the package can be found in *The Warning Package*. This package can be useful to detect an abort

A printing utility is available in the driver that can be helpful when debugging the code. Not all of these will work everywhere in the code, due to possible conflicts in module dependencies.

***debug_icepack* (configuration/driver/ice_diagnostics.F90)** A wrapper for *print_state* that is easily called from numerous points during initialization and the timestepping loop

***print_state* (configuration/driver/ice_diagnostics.F90)** Print the ice state and forcing fields for a given grid cell.

3.5.4 Known bugs and other issues

- With the old CCSM radiative scheme (`shortwave = 'default' or 'ccsm3'`), a sizable fraction (more than 10%) of the total shortwave radiation is absorbed at the surface but should be penetrating into the ice interior instead. This is due to use of the aggregated, effective albedo rather than the bare ice albedo when `snowpatch < 1`.
- The linear remapping algorithm for thickness is not monotonic for tracers.
- The form drag parameterization assumes a fixed ridge shape where both the macroscopic ridge porosity and the angle of repose are specified parameters. One high-resolution coupled model that uses the CICE column physics package has been unable to make this parameterization work in its current form. Development of a new, variational approach for ridging is underway that will generate ridge shapes differently from the current parameterization, and is expected to alleviate the reported problem (Roberts, A., et al, in prep. 2018).

3.5.5 Interpretation of albedos

The snow-and-ice albedo, `albsni`, and diagnostic albedos `albice`, `albsno`, and `albpnd` are merged over categories but not scaled (divided) by the total ice area. (This is a change from CICE v4.1 for `albsni`.) The latter three history variables represent completely bare or completely snow- or melt-pond-covered ice; that is, they do not take into account the snow or melt pond fraction (`albsni` does, as does the code itself during thermodynamic computations). This is to facilitate comparison with typical values in measurements or other albedo parameterizations. The melt pond albedo `albpnd` is only computed for the Delta-Eddington shortwave case.

With the Delta-Eddington parameterization, the albedo depends on the cosine of the zenith angle ($\cos \varphi$, `coszen`) and is zero if the sun is below the horizon ($\cos \varphi < 0$). Therefore time-averaged albedo fields would be low if a diurnal solar cycle is used, because zero values would be included in the average for half of each 24-hour period. To rectify this, a separate counter is used for the averaging that is incremented only when $\cos \varphi > 0$. The albedos will still be zero in the dark, polar winter hemisphere.

3.5.6 Interpretation of general results

Icepack releases are “functional releases” in the sense that the code runs, does not crash, passes various tests, and requires further work to establish its scientific validity. In general, users are not encouraged to use any of the CICE Consortium’s model configurations to obtain “scientific” results. The test configurations are useful for model development, but sea ice models must be evaluated from a physical standpoint in a couple system because simplified configurations do not necessarily represent what is actually happening in the fully coupled system that includes interactive ocean and atmosphere components.

3.5.7 Proliferating subprocess parameterizations

With the addition of several alternative parameterizations for sea ice processes, a number of subprocesses now appear in multiple parts of the code with differing descriptions. For instance, sea ice porosity and permeability, along with associated flushing and flooding, are calculated separately for mushy thermodynamics, topo and level-ice melt ponds, and for the brine height tracer, each employing its own equations. Likewise, the BL99 and mushy thermodynamics compute freeboard and snow–ice formation differently, and the topo and level-ice melt pond schemes both allow

fresh ice to grow atop melt ponds, using slightly different formulations for Stefan freezing. These various process parameterizations will be compared and their subprocess descriptions possibly unified in the future.

DEVELOPER GUIDE

4.1 About Development

The Icepack model consists of three different parts, the column physics code, the icepack driver, and the scripts. Development of each of these pieces will be described below separately.

Subroutine calls and other linkages into Icepack from the host model should only need to access the **icepack_intfc*.F90** interface modules within the `columnphysics/` directory. The Icepack driver in the `configuration/driver/` directory is based on the CICE model and provides an example of the sea ice host model capabilities needed for inclusion of Icepack. In particular, host models will need to include code equivalent to that in the modules **icedrv_*_column.F90**. Calls into the Icepack interface routines are primarily from **icedrv_step_mod.F90** but there are others (search the driver code for `intfc`).

Guiding principles for the creation of Icepack include the following:

- The column physics modules shall be independent of all sea ice model infrastructural elements that may vary from model to model. Examples include input/output, timers, references to CPUs or computational tasks, initialization other than that necessary for strictly physical reasons, and anything related to a horizontal grid.
- The column physics modules shall not call or reference any routines or code that reside outside of the **columnphysics/** directory.
- Any capabilities required by a host sea ice model (e.g. calendar variables, tracer flags, diagnostics) shall be implemented in the driver and passed into or out of the column physics modules via array arguments.

4.2 Icepack Column Physics

4.2.1 File List

The column physics source code contains the following files

columnphysics/ the column physics code

icepack_aerosol.F90 handles most work associated with the aerosol tracers

icepack_age.F90 handles most work associated with the age tracer

icepack_algae.F90 biogeochemistry

icepack_atmo.F90 stability-based parameterization for calculation of turbulent ice–atmosphere fluxes

icepack_brine.F90 evolves the brine height tracer

icepack_firstyear.F90 handles most work associated with the first-year ice area tracer

icepack_flux.F90 fluxes needed/produced by the model

icepack_intfc.F90 interface routines for linking Icepack with a host sea ice model
icepack_itd.F90 utilities for managing ice thickness distribution
icepack_kinds.F90 basic definitions of reals, integers, etc.
icepack_mechred.F90 mechanical redistribution (ridging)
icepack_meltpond_cesm.F90 CESM melt pond parameterization
icepack_meltpond_lvl.F90 level-ice melt pond parameterization
icepack_meltpond_topo.F90 topo melt pond parameterization
icepack_mushy_physics.F90 physics routines for mushy thermodynamics
icepack_ocean.F90 mixed layer ocean model
icepack_orbital.F90 orbital parameters for Delta-Eddington shortwave parameterization
icepack_parameters.F90 basic model parameters including physical and numerical constants required for column package
icepack_shortwave.F90 shortwave and albedo parameterizations
icepack_therm_0layer.F90 zero-layer thermodynamics of [46]
icepack_therm_bl99.F90 multilayer thermodynamics of [6]
icepack_therm_itd.F90 thermodynamic changes mostly related to ice thickness distribution
icepack_therm_mushy.F90 mushy-theory thermodynamics of [53]
icepack_therm_shared.F90 code shared by all thermodynamics parameterizations
icepack_therm_vertical.F90 vertical growth rates and fluxes
icepack_tracers.F90 tracer information
icepack_warnings.F90 utilities for writing warning and error messages
icepack_zbgc.F90 driver for ice biogeochemistry and brine tracer motion
icepack_zbgc_shared.F90 parameters and shared code for biogeochemistry and brine height
icepack_zsalinity.F90 vertical salinity parameterization of [25]

4.2.2 Coding Standard

The column physics is a library that solves the sea ice column physics on a timestep by timestep and gridpoint by gridpoint basis. It consists of Fortran routines with input and output arguments. The model state is saved in the host model. There is no communication between gridcells so the underlying implementation supports no parallelization. It however can be called in parallel by a driver that is running on multiple pes with a decomposed grid.

The column physics does not have a time manager. Calendaring is expected to be dealt with by the host model. The column physics does not read any forcing data, that is passed into the column physics through interfaces. In fact, there are no direct IO capabilities in the column physics. That is to say, the column physics does not open files to read or write. The column physics is able to write data via several different routines that specifically have a fortran unit number as an input argument. In addition, there is a warning package (see section *The Warning Package*) that provides the column package with the ability to store log output. That output can be queried by the host model or it can be written directly via a specific routine. The warning package also provides access to an abort flag that the host model can query after each call to check for successful completion of the column physics package.

All column physics public interfaces and public data are defined in the **icepack_intfc.F90** file. Internal column physics settings should all be accessible through interfaces. The internal constants, parameters, and tracer settings have init (set), query (get), and write interfaces that provides access to internal column physics settings. The host model should not have to use “use” statements to access any of the column physics data outside of what is provided through the icepack_intfc module. The public column physics interfaces use optional arguments where it makes sense and there is an ongoing effort to make more of the interfaces support keyword=value arguments for clarity and backwards compatibility.

4.2.3 Using Icepack

In this section, the various public icepack interfaces will be defined and how to use them will be described.

Interfaces

Column physics data and subroutines are made public through the **icepack_intfc.F90** file. That file contains the entire list of data and subroutines needed to initialize, setup, and run the column physics package. That file points to other modules within the column physics where the interfaces are located.

Within **icepack_intfc.F90**, internal icepack kinds are defined via the `icepack_kinds` module:

```
use icepack_kinds, only: icepack_char_len  => char_len
use icepack_kinds, only: icepack_char_len_long  => char_len_long
use icepack_kinds, only: icepack_log_kind  => log_kind
use icepack_kinds, only: icepack_int_kind  => int_kind
use icepack_kinds, only: icepack_real_kind  => real_kind
use icepack_kinds, only: icepack_dbl_kind  => dbl_kind
use icepack_kinds, only: icepack_r16_kind  => r16_kind
```

`icepack_tracers` defines a handful of parameters that provide information about maximum array sizes for static dimensioning:

```
use icepack_tracers,    only: icepack_max_nbtrcr => max_nbtrcr
use icepack_tracers,    only: icepack_max_algae  => max_algae
use icepack_tracers,    only: icepack_max_dic    => max_dic
use icepack_tracers,    only: icepack_max_doc    => max_doc
use icepack_tracers,    only: icepack_max_don    => max_don
use icepack_tracers,    only: icepack_max_fe     => max_fe
use icepack_tracers,    only: icepack_max_aero   => max_aero
use icepack_tracers,    only: icepack_nmodal1    => nmodal1
use icepack_tracers,    only: icepack_nmodal2    => nmodal2
use icepack_parameters, only: icepack_nspint     => nspint
```

`icepack_parameters` provides `init`, `query`, `write`, and `recompute` methods to define constant values and model parameters. These constants have defaults that the caller can query or reset:

```
use icepack_parameters, only: icepack_init_parameters
use icepack_parameters, only: icepack_query_parameters
use icepack_parameters, only: icepack_write_parameters
use icepack_parameters, only: icepack_recompute_constants
```

`icepack_tracers` provides `init`, `query`, and `write` methods to define various tracer sizes, flags, indices, and numbers. The tracers have some defaults that the caller can query or reset:

```
use icepack_tracers, only: icepack_compute_tracers
use icepack_tracers, only: icepack_query_tracer_sizes
use icepack_tracers, only: icepack_write_tracer_sizes
use icepack_tracers, only: icepack_init_tracer_flags
use icepack_tracers, only: icepack_query_tracer_flags
use icepack_tracers, only: icepack_write_tracer_flags
use icepack_tracers, only: icepack_init_tracer_indices
use icepack_tracers, only: icepack_query_tracer_indices
use icepack_tracers, only: icepack_write_tracer_indices
use icepack_tracers, only: icepack_init_tracer_numbers
use icepack_tracers, only: icepack_query_tracer_numbers
use icepack_tracers, only: icepack_write_tracer_numbers
```

`icepack_itd` provides three public interfaces to compute the ice thickness distribution:

```
use icepack_itd, only: icepack_init_itd
use icepack_itd, only: icepack_init_itd_hist
use icepack_itd, only: icepack_aggregate
```

`icepack_mechred` contains two public interfaces to compute ridging and ice strength:

```
use icepack_mechred, only: icepack_step_ridge
use icepack_mechred, only: icepack_ice_strength
```

`icepack_shortwave` provides a routine to initialize the radiation computation and an routine to update the radiation computation:

```
use icepack_shortwave, only: icepack_prep_radiation
use icepack_shortwave, only: icepack_step_radiation
```

`icepack_brine` address brine and zsalinity computations:

```
use icepack_brine, only: icepack_init_hbrine
use icepack_brine, only: icepack_init_zsalinity
```

`icepack_zbgc` contains several public interfaces to support initialization and computation for the skeletal layer bgc and zbgc options:

```
use icepack_zbgc , only: icepack_init_bgc
use icepack_zbgc , only: icepack_init_zbgc
use icepack_zbgc , only: icepack_biogeochemistry
use icepack_zbgc , only: icepack_init_OceanConcArray
use icepack_zbgc , only: icepack_init_ocean_conc
```

There are a couple of routines to support computation of an atmosphere and ocean interaction:

```
use icepack_atmo , only: icepack_atm_boundary
use icepack_ocean, only: icepack_ocn_mixed_layer
```

`icepack_step_therm1` and `icepack_step_therm2` compute the ice thermodynamics in two steps:

```
use icepack_therm_vertical, only: icepack_step_therm1
use icepack_therm_itd      , only: icepack_step_therm2
```

`icepack_therm_shared` provides several methods to compute different internal terms:

```
use icepack_therm_shared , only: icepack_ice_temperature
use icepack_therm_shared , only: icepack_snow_temperature
use icepack_therm_shared , only: icepack_liquidus_temperature
use icepack_therm_shared , only: icepack_sea_freezing_temperature
use icepack_therm_shared , only: icepack_enthalpy_snow
use icepack_therm_shared , only: icepack_init_thermo
use icepack_therm_shared , only: icepack_init_trcr
```

`icepack_orbital` provides a routine to set orbital parameters needed for some albedo computations:

```
use icepack_orbital , only: icepack_init_orbit
```

`icepack_warnings` provides several methods for getting, writing, and clearing messages. There is also a function that returns a logical flag indicating whether the column physics has aborted:


```

use icepack_warnings, only: icepack_warnings_clear
use icepack_warnings, only: icepack_warnings_getall
use icepack_warnings, only: icepack_warnings_print
use icepack_warnings, only: icepack_warnings_flush
use icepack_warnings, only: icepack_warnings_aborted

```

icepack_configure is a standalone icepack method that should always be called first:

```

public :: icepack_configure

```

Calling Sequence

The calling sequence required to setup and run the column physics is generally described below. Several steps may be needed to be taken by the host between icepack calls in order to support the icepack interfaces. The icepack driver and the CICE model provide working examples of how to do this in practice. The sample below does not include bgc.

start driver

- call *icepack_configure*

initialize driver and read in driver namelist

- call *icepack_init_parameters*
- call *icepack_init_tracers_*
- call *icepack_init_trcr*
- call *icepack_init_thermo*
- call *icepack_init_itd*
- call *icepack_init_itd_hist*
- call *icepack_step_radiation*
- call *icepack_init_zsalinity*
- call *icepack_init_hbrine*
- call *icepack_aggregate*

loop over timesteps loop over gridcells

- call *icepack_prep_radiation*
- call *icepack_step_therm1*
- call *icepack_step_therm2*
- call *icepack_aggregate*
- call *icepack_step_ridge*
- call *icepack_step_radiation*
- call *icepack_atm_boundary*
- call *icepack_ocn_mixed_layer*

end loop over gridcells end loop over timesteps

end driver

The Warning Package

Icepack has no IO capabilities. It does not have direct knowledge of any input or output files. However, it can write output through specific interfaces that pass in a fortran file unit number. There are several methods in icepack that support writing data to a file this way including the various *icepack_write_* interfaces.

Separately, the icepack warning package is where icepack stores internal output and error messages not directly set in the various write routines. The warning package also contains an *icepack_warnings_aborted* function that will be set to true if icepack detects an abort. In that case, icepack will return to the driver. As a general rule, after each call to icepack, the driver should call:

```
call icepack_warnings_flush(nu_diag)
if (icepack_warnings_aborted()) call icedrv_system_abort(string=subname, &
    file=__FILE__, line=__LINE__)
```

to flush (print and clear) the icepack warning buffer and to check whether icepack aborted. If icepack aborts, it's actually up to the driver to cleanly shut the model down.

Alternatively, *icepack_warnings_getall* provides the saved icepack messages to the driver via an array of strings in the argument list. This allows the driver to reformat that output as needed. *icepack_warnings_print* writes out the messages but does not clear them, and *icepack_warnings_clear* zeros out the icepack warning messages.

4.3 Driver Implementation

The icepack driver is Fortran source code and exists to test the column physics in a stand-alone mode for some simple column configurations.

4.3.1 File List

The icepack driver consists of the following files

configuration/driver/ driver for testing Icepack in stand-alone mode

- icedrv_MAIN.F90** main program
- icedrv_InitMod.F90** routines for initializing a run
- icedrv_RunMod.F90** main driver routines for time stepping
- icedrv_arrays_column.F90** essential arrays to describe the state of the ice
- icedrv_calendar.F90** keeps track of what time it is
- icedrv_constants.F90** physical and numerical constants and parameters
- icedrv_diagnostics.F90** miscellaneous diagnostic and debugging routines
- icedrv_diagnostics_bgc.F90** diagnostic routines for biogeochemistry
- icedrv_domain_size.F90** domain sizes
- icedrv_flux.F90** fluxes needed/produced by the model
- icedrv_forcing.F90** routines to read and interpolate forcing data for stand-alone model runs
- icedrv_forcing_bgc.F90** routines to read and interpolate forcing data for bgc stand-alone model runs
- icedrv_init.F90** general initialization routines
- icedrv_init_column.F90** initialization routines specific to the column physics
- icedrv_restart.F90** driver for reading/writing restart files
- icedrv_restart_bgc.F90** restart routines specific to the column physics
- icedrv_restart_shared.F90** code shared by all restart options

icedrv_state.F90 essential arrays to describe the state of the ice
icedrv_step.F90 routines for time stepping the major code components
icedrv_system.F90 overall system management calls

4.3.2 Overview

The icepack driver exists to test the column physics. At the present time, it is hardwired to run 4 different gridcells on one processor with the same forcing used for all gridcells. There is no MPI and no threading built into the icepack driver. There is limited IO capabilities, no history files, and no netcdf restart files. The model generally runs very quickly.

Forcing data and details on these data are available in *Forcing data*.

4.4 Scripts Implementation

The scripts are the third part of the icepack package. They support setting up cases, building, and running the icepack stand-alone model.

4.4.1 File List

The directory structure under configure/scripts is as follows.

configuration/scripts/

- Makefile** primary makefile
- icepack.batch.csh** creates batch scripts for particular machines
- icepack.build** compiles the code
- icepack.launch.csh** creates script logic that runs the executable
- icepack.run.setup.csh** sets up the run scripts
- icepack.run.suite.csh** sets up the test suite
- icepack.settings** defines environment, model configuration and run settings
- icepack.test.setup.csh** creates configurations for testing the model
- icepack_decomp.csh** defines the grid size
- icepack_in** namelist input data
- machines/** machine specific files to set env and Macros
- makdep.c** determines module dependencies
- options/** other namelist configurations available from the icepack.setup command line
- parse_namelist.sh** replaces namelist with command-line configuration
- parse_namelist_from_settings.sh** replaces namelist with values from icepack.settings
- parse_settings.sh** replaces settings with command-line configuration
- tests/** scripts for configuring and running basic tests

4.4.2 Strategy

The icepack scripts are implemented such that everything is resolved after **icepack.setup** is called. This is done by both copying specific files into the case directory and running scripts as part of the **icepack.setup** command line to setup various files.

icepack.setup drives the case setup. It is written in csh. All supporting scripts are relatively simple csh or sh scripts.

The file **icepack.settings** specifies a set of env defaults for the case. The file **icepack_in** defines the namelist input for the icepack driver.

4.4.3 Preset Case Options

icepack.setup -s option allows the user to choose some predetermined icepack settings and namelist. Those options are defined in **configurations/scripts/options/** and the files are prefixed by either **set_env**, **set_nml**, or **test_nml**. When **icepack.setup** is executed, the appropriate files are read from **configurations/scripts/options/** and the **icepack.settings** and/or **icepack_in** files are updated in the case directory based on the values in those files.

The filename suffix determines the name of the -s option. So, for instance,

```
icepack.setup -s diag1,debug,bgcISPOL
```

will search for option files with suffixes of **diag1**, **debug**, and **bgcISPOL** and then apply those settings.

parse_namelist.sh, **parse_settings.sh**, and **parse_namelist_from_settings.sh** are the three scripts that modify **icepack_in** and **icepack.settings**.

To add new options, just add new files to the **configurations/scripts/options/** directory with appropriate names and syntax. The **set_nml** file syntax is the same as namelist syntax and the **set_env** files are consistent with csh **setenv** syntax. See other files for examples of the syntax.

4.4.4 Machines

Machine specific information is contained in **configuration/scripts/machines**. That directory contains a **Macros** file and an **env** file for each supported machine. One other files will need to be changed to support a port, that is **configuration/scripts/icepack.batch.csh**. To port to a new machine, see [Porting](#).

4.4.5 Test scripts

Under **configuration/scripts/tests** are several files including the scripts to setup the smoke and restart tests (**test_smoke.script**, **test_restart.script**). A **baseline test script** (****baseline.script**) is also there to setup the regression and comparison testing. That directory also contains the preset test suites (ie. **base_suite.ts**) and a file that supports post-processing on the model output (**timeseries.csh**).

There is a subdirectory, **configuration/scripts/tests/CTest**, that supports the CTest scripts. These scripts allow test reporting to CDash.

To add a new test, a file associated with that test will need to be added to the **configuration/scripts/tests** directory similar to **test_smoke.script** and **test_restart.script**. In addition, some new options files in **configuration/scripts/options** may need to be added similar to **test_nml.restart1**, **test_nml.restart2**, and **set_nml.restart**.

4.5 Adding tracers

We require that any changes made to the code be implemented in such a way that they can be “turned off” through namelist flags. In most cases, code run with such changes should be bit-for-bit identical with the unmodified code. Occasionally, non-bit-for-bit changes are necessary, e.g. associated with an unavoidable change in the order of operations. In these cases, changes should be made in stages to isolate the non-bit-for-bit changes, so that those that should be bit-for-bit can be tested separately.

Tracers added to Icepack will also require extensive modifications to the host sea ice model, including initialization on the horizontal grid, namelist flags and restart capabilities. Modifications to the Icepack driver should reflect the modifications needed in the host model but are not expected to match completely. We recommend that the logical namelist variable `tr_[tracer]` be used for all calls involving the new tracer outside of `ice_[tracer].F90`, in case other users do not want to use that tracer.

A number of optional tracers are available in the code, including ice age, first-year ice area, melt pond area and volume, brine height, aerosols, and level ice area and volume (from which ridged ice quantities are derived). Salinity, enthalpies, age, aerosols, level-ice volume, brine height and most melt pond quantities are volume-weighted tracers, while first-year area, pond area, level-ice area and all of the biogeochemistry tracers in this release are area-weighted tracers. In the absence of sources and sinks, the total mass of a volume-weighted tracer such as aerosol (kg) is conserved under transport in horizontal and thickness space (the mass in a given grid cell will change), whereas the aerosol concentration (kg/m) is unchanged following the motion, and in particular, the concentration is unchanged when there is surface or basal melting. The proper units for a volume-weighted mass tracer in the tracer array are kg/m.

In several places in the code, tracer computations must be performed on the conserved “tracer volume” rather than the tracer itself; for example, the conserved quantity is $h_{pnd}a_{pnd}a_{lvl}a_i$, not h_{pnd} . Conserved quantities are thus computed according to the tracer dependencies, and code must be included to account for new dependencies (e.g., a_{lvl} and a_{pnd} in `ice_itd.F90` and `ice_mechred.F90`).

To add a tracer, follow these steps using one of the existing tracers as a pattern.

1. **icedrv_domain_size.F90**: increase `max_ntrcr` (can also add option to `icepack.settings` and `icepack.build`)
2. **icedrv_state.F90**: declare `nt_[tracer]` and `tr_[tracer]`
3. **icepack_[tracer].F90**: create initialization, physics routines
4. **ice_drv_init.F90**: (some of this may be done in `ice_[tracer].F90` instead)
 - add new module and `tr_[tracer]` to list of used modules and variables
 - add logical namelist variable `tr_[tracer]`
 - initialize namelist variable
 - print namelist variable to diagnostic output file
 - increment number of tracers in use based on namelist input (`ntrcr`)
 - define tracer types (`trcr_depend = 0` for ice area tracers, 1 for ice volume, 2 for snow volume, 2+‘nt_‘[tracer] for dependence on other tracers)
5. **icepack_itd.F90**, **icepack_mechred.F90**: Account for new dependencies if needed.
6. **icedrv_InitMod.F90**: initialize tracer (includes reading restart file)
7. **icedrv_RunMod.F90**, **icedrv_step_mod.F90**:
 - call routine to write tracer restart data
 - call physics routines in `icepack_[tracer].F90` (often called from `icedrv_step_mod.F90`)
8. **icedrv_restart.F90**: define restart variables
9. **icepack_in**: add namelist variables to `tracer_nml` and `icefields_nml`
10. If strict conservation is necessary, add diagnostics as noted for topo ponds in Section [Melt ponds](#).

4.6 Documentation System

With Icepack development, corresponding updates or modification to the Icepack documentation are required. Whenever you modify the model you should update documentation. Icepack uses Sphinx to create online HTML documentation.

4.6.1 FAQs

1. What are Sphinx and reStructuredText (RST)?

The CICE and Icepack documentation is written using reStructuredText (RST) markup language. ReStructuredText is a markup language, like HTML, markdown or LaTeX. Sphinx is a python tool for publishing RST documents in other formats such as HTML and PDF. Additional information about using RST and Sphinx are found in the sections below.

2. What is expected of *me* when changing the documentation?

We expect that if you need to add or modify documentation that you will be able to modify the RST source files and generate HTML using Sphinx in order to review the HTML documentation. We will review the RST and HTML during a Pull Request to verify it is working properly and is consistent with the rest of the CICE-Consortium documentation format.

We do not expect you to generate a PDF of your documentation changes and include this as part of a Pull Request. Updated PDF documentation will be generated for each new release. The online HTML documentation, however, will be updated regularly with regular code development workflow.

3. Where are the documentation files kept?

A PDF of the latest release documentation is available in the master branch at `/doc/Icepack-v*.pdf`. This document is generated by the CICE-Consortium team and will be updated with releases. The HTML on the website is kept up to date with the developing code, and is therefore updated more often than the PDF.

The RST source files for generating html are stored in the master branch of the repository under `/doc/source/`.

On your local fork, when you modify RST and use it to generate HTML, the HTML files are created in the `/doc/build/html/` directory and can be opened locally for review as you modify the documentation.

For the CICE Consortium, the tested and vetted HTML pages brought in through successful Pull Requests are stored in the `gh-pages` branch of the repository and accessible from the URL to the linked, searchable User's Guide on in the README.md file at the top level of the Icepack repository or on the main wiki page for Icepack (<https://github.com/CICE-Consortium/Icepack/wiki>). Note that `gh-pages` is an orphan branch (see below for details) of the repository and has *only* the Sphinx generated HTML documentation and nothing else.

4.6.2 Steps for Modifying Documentation

Installing Sphinx

This must be done once on each platform. See [Sphinx](#) or [Installing Sphinx](#) for details. Below are the commands for installing Sphinx on a mac laptop at the command line. Other platforms may require other steps.

```
$ sudo pip install --ignore-installed sphinx
$ sudo pip install --ignore-installed sphinxcontrib-bibtex
```

The CICE Consortium uses the following software to get successful Sphinx HTML builds, including linked references:

- python 2.7.11

- Sphinx (1.6.3)
- sphinx-rtd-theme (0.1.9)
- sphinxcontrib-bibtex (0.3.5)
- sphinxcontrib-websupport (1.0.1)

You will need to use the CICE Consortium’s `conf.py` file, which is found under `/doc/source/conf.py` in the repository in order to build the Sphinx documentation.

To use linked references within the HTML you will need to have the `sphinxcontrib-bibtex` package as well as the `zreferences.rst` and `master_list.bib` files located in `/doc/source/` in the master repository. The list of references in `master_list.bib` is currently ordered sequentially from oldest to newest and alphabetically within a given year. To add references for your documentation, edit the `master_list.bib` file using the Articles and Books as examples for your addition(s). Please follow the format for ordering the date/alphabetization as well as including a URL with the document’s DOI.

Model sandbox and documentation

Follow the general [CICE-Consortium Git Workflow and Developer’s guide](#) to clone the repository and create your personal fork for model modifications. Whenever you modify the model you should update documentation. You can update the documentation on the same branch of your fork on which you test code, or you can create a separate branch called `documentation` to test only the RST and HTML documentation.

Editing RST files

Open the RST file using a text editor and make the changes necessary. Note that from the User’s Guide documentation (see link above) there is a hyperlink called “Show Source” on the left hand column that will show you the RST source code for the HTML you are viewing. This is a good way to see the syntax for tables, equations, linking references, labeling tables or figures, and correctly identifying documentation sections or subsections.

Here are some resources for using RST files:

- [RST Primer1](#)
- [RST Primer2](#)
- [RST Syntax](#)
- [RST tables](#) - Note that tables can be tricky in Sphinx and we prefer using [comma separated tables](#) whenever possible.

Building HTML

Move into the `/doc/` directory of your sandbox. Then execute the following command:

```
$ make clean
```

to get rid of old HTML files. Then execute:

```
$ make html
```

to build HTML into `/build/html/` directory. It will also give you errors if there is a problem with the build that will help you figure out how you need to modify your RST files for a successful HTML build. Finally

```
$ open /build/html/FILE.html
```

Open the HTML on your browser for testing.

Push changes back to the repository

When you're happy with the HTML you've generated, follow the standard CICE-Consortium [Git Workflow and Developer's guide](#) to do a Pull Request and make sure to note in the Pull Request Template that documentation has also been updated. We will take care of testing and adding changed HTML to the gh-pages orphan branch.

4.6.3 Other Tips and Tricks

Converting LaTeX to RST

If you start from a LaTeX (`*.tex`) document you will need to convert this to the RST format that Sphinx requires. A handy tool to do this is [Pandoc](#), which you can install quickly and run from the command line.

Once Pandoc is installed, the basic command line syntax to convert a file is

```
$ pandoc NAMEIN.tex -f latex -t rst -s -ou NAMEOUT.rst
```

The NAMEOUT.rst file can be directly edited for Sphinx. Pandoc does a beautiful job of converting the text, equations, and many tables. However, equation numbering, section linking, references, figures, and some tables required more hands on care to be sure they render correctly.

Pandoc requires that the `*.tex` files be in utf-8 encoding. To easily do this open the `*.tex` document in Emacs then do `ctrl-x ctrl-m f` and you will be prompted to enter encoding type. Just type in `utf-8` and hit enter. Then save with `ctrl-x ctrl-s`. You are done and the document can be converted with Pandoc.

Converting RST to PDF

Generating a PDF is more complex and currently requires a two-step process. The generation will require recent versions of both LaTeX and Sphinx. From the `/doc/` directory do the following:

```
$ make latex
$ cd build/latex
$ make
```

Then search for the `*.pdf` document created.

Creating an orphan branch

THIS STEP SHOULD NOT BE REQUIRED FOR ANY ADDITIONS TO DOCUMENTATION BUT A DESCRIPTION IS PROVIDED IN THE INTEREST OF TRANSPARENCY AND REPRODUCIBILITY FOR THE BENEFIT OF USERS AND THE COMMUNITY

An orphan branch is a branch that has no history in common with the master repository off of which it was forked. For the CICE-Consortium, the purpose for this is that the HTML pages created by Sphinx will exist in the orphan branch while the source RST code used to create the HTML exists in the master repository. This way changes to the RST go into the evolving repository, but changes to the HTML are isolated to the orphan branch. This method avoids conflicts related to the HTML that aren't always caught by GitHub merges and could cause the documentation to break.

Steps to create orphan branch:

1. On GitHub website create personal fork of the repo you're interested in
2. On GitHub website from your fork, get link for the repository

3. On your local machine execute the following commands:

Clone the original repository.

```
$ git clone URL
```

List all the branches of the repository.

```
$ git branch --l
```

Create the orphan branch gh-pages from the master branch. The branch should initially have all documents from the master.

```
$ git checkout --orphan gh-pages
```

Add the URL for the original repository as your “upstream” repository. Get this from Github website.

```
$ git remote add upstream URL
```

Remove everything in this repository. i.e. we are making it so their histories diverge.

```
$ git rm -rf .
```

Check if all the files are gone.

```
$ git status .
```

Commit the change to make gh-pages branch.

```
$ git commit -m "Initial commit to create gh-pages branch of repo"
```

Provide a list of remote repositories and links. Should show your personal fork as “origin” and the original repository as “upstream”.

```
$ git remote --v
```

Add the orphan branch, named gh-pages, to your local fork but not the original repo from which you forked.

```
$ git push origin gh-pages
```

4. Once you’ve created the gh-pages branch on your personal fork do a pull request to incorporate the new branch into the master repository. This way someone else will review what you’ve done and make sure you don’t delete an entire repository by accident. It is possible to push the gh-pages branch upstream if you have owner status; **be very careful if you do this.**
5. For a new orphan branch, set up sphinx stuff by executing the following commands:

Go to doc directory.

```
$ cd doc
```

Make a source directory.

```
$ mkdir source
```

Initiate sphinx interactive session to create a conf.py file. Note that the conf.py file can be changed later on.

```
$ sphinx-quickstart
```

Answer the prompts

Set GitHub to ignore HTML and Emacs back up files during commits, pushes, and pull requests.

```
$ cp .gitignore from CICE-Consortium CICE or Icepack master repository
```

Add the two new files (conf.py, .gitignore).

```
$ git add .
```

Commit the changes.

```
$ git commit -m "Initial setup for Sphinx documentation"
```

6. Do a pull request to add these to the master repository.

INDEX OF PRIMARY VARIABLES AND PARAMETERS

This index defines many of the symbols used frequently in the ice model code. Values appearing in this list are fixed or recommended; most namelist parameters are indicated (E_o) with their default values. For other namelist options, see Section [Table of Namelist Inputs](#). All quantities in the code are expressed in MKS units (temperatures may take either Celsius or Kelvin units).

Table 5.1: *Alphabetical Index of Icespack Variables and Parameters*

A			
a_rapid_mode	• brine channel diameter		
ahmax	• thickness above which ice albedo is constant	0.3m	
aice_init	concentration of ice at beginning of timestep		
aice0	fractional open water area		
aice(n)	total concentration of ice in grid cell (in category n)		
albedo_type	• type of albedo parameterization ('default' or 'constant')		
albice	bare ice albedo		
albice_i	• near infrared ice albedo for thicker ice		
albice_v	• visible ice albedo for thicker ice		
albocn	ocean albedo	0.06	
albpnd	melt pond albedo		
albsno	snow albedo		
albsnow_i	• near infrared, cold snow albedo		
albsnow_v	• visible, cold snow albedo		
algalN	algal nitrogen concentration	mmol/m ³	
alndf	albedo: near IR, diffuse		
alndr	albedo: near IR, direct		
alvdf	albedo: visible, diffuse		
alvdr	albedo: visible, direct		
alndf_ai	grid-box-mean value of alndf		
alndr_ai	grid-box-mean value of alndr		
alvdf_ai	grid-box-mean value of alvdf		
alvdr_ai	grid-box-mean value of alvdr		
amm	ammonia/um concentration	mmol/m ³	
aparticn	participation function		
apeff_ai	grid-cell-mean effective pond fraction		
apondn	area concentration of melt ponds		
araftn	area fraction of rafted ice		
ardgn	fractional area of ridged ice		

Continued on next page

Table 5.1 – continued from previous page

aspect_rapid_mode	• brine convection aspect ratio	1	
astar	e-folding scale for participation function	0.05	
atm_data_format	• format of atmospheric forcing files		
atm_data_type	• type of atmospheric forcing		
atmbndy	• atmo boundary layer parameterization ('default' or 'constant')		
awtidf	weighting factor for near-ir, diffuse albedo	0.36218	
awtidr	weighting factor for near-ir, direct albedo	0.00182	
awtvdf	weighting factor for visible, diffuse albedo	0.63282	
awtvdr	weighting factor for visible, direct albedo	0.00318	
B			
bgc_data_dir	• data directory for bgc		
bgc_data_type	• forcing type for biogeochemistry		
bgc_flux_type	• ice-ocean flux velocity type		
bgc_tracer_type	tracer_type for bgc tracers		
bgrid	nondimensional vertical grid points for bio grid		
bignum	a large number	10^{30}	
bphi	porosity of ice layers on bio grid		
bTiz	temperature of ice layers on bio grid		
C			
calc_strair	• if true, calculate wind stress	T	
calc_Tsfc	• if true, calculate surface temperature	T	
Cdn_atm	atmospheric drag coefficient		
Cdn_ocn	ocean drag coefficient		
Cf	• ratio of ridging work to PE change in ridging	17.	
cgrid	vertical grid points for ice grid (compare bgrid)		
char_len	length of character variable strings	80	
char_len_long	length of longer character variable strings	256	
check_step	time step on which to begin writing debugging data		
cldf	cloud fraction		
cm_to_m	cm to meters conversion	0.01	
coldice	value for constant albedo parameterization	0.70	
coldsnow	value for constant albedo parameterization	0.81	
conduct	• conductivity parameterization		
congel	basal ice growth	m	
coszen	cosine of the zenith angle		
Cp	proportionality constant for potential energy	$\text{kg/m}^2/\text{s}^2$	
cp_air	specific heat of air	1005.0 J/kg/K	
cp_ice	specific heat of fresh ice	2106. J/kg/K	
cp_ocn	specific heat of sea water	4218. J/kg/K	
cp_wv	specific heat of water vapor	1.81×10^3 J/kg/K	
cp063	diffuse fresnel reflectivity (above)	0.063	
cp455	diffuse fresnel reflectivity (below)	0.455	

Continued on next page

Table 5.1 – continued from previous page

Cs	fraction of shear energy contributing to ridging	0.25
Cstar	constant in Hibler ice strength formula	20.
D		
daice_da	data assimilation concentration increment rate	
daiddt	ice area tendency due to dynamics/transport	1/s
daiddt	ice area tendency due to thermodynamics	1/s
dalb_mlt	[see ice_shortwave.F90]	-0.075
dalb_mlti	[see ice_shortwave.F90]	-0.100
dalb_mltv	[see ice_shortwave.F90]	-0.150
darcy_V	Darcy velocity used for brine height tracer	
dardg1(n)dt	rate of fractional area loss by ridging ice (category n)	1/s
dardg2(n)dt	rate of fractional area gain by new ridges (category n)	1/s
daymo	number of days in one month	
daycal	day number at end of month	
days_per_year	• number of days in one year	365
dbl_kind	definition of double precision	selected_real_kind(13)
debug	• write extra diagnostics	.false.
depressT	ratio of freezing temperature to salinity of brine	0.054 deg/ppt
dhbr_bt	change in brine height at the bottom of the column	
dhbr_top	change in brine height at the top of the column	
dhsn	depth difference for snow on sea ice and pond ice	
diag_file	• diagnostic output file (alternative to standard out)	
diagfreq	• how often diagnostic output is written (10 = once per 10 dt)	
divu	strain rate I component, velocity divergence	1/s
divu_adv	divergence associated with advection	1/s
dms	dimethyl sulfide concentration	mmol/m ³
dmsp	dimethyl sulfoniopropionate concentration	mmol/m ³
dpscale	• time scale for flushing in permeable ice	1×10^{-3}
dragio	drag coefficient for water on ice	0.00536
dSdt_slow_mode	• drainage strength parameter	
dsnow	change in snow thickness	m
dt	• thermodynamics time step	3600. s
dt_dyn	dynamics/ridging/transport time step	
dT_mlt	• Δ temperature per Δ snow grain radius	1. deg
dumpfreq	• dump frequency for restarts, y, m or d	
dumpfreq_n	• restart output frequency	
dvidtd	ice volume tendency due to dynamics/transport	m/s
dvidtt	ice volume tendency due to thermodynamics	m/s
dvirdg(n)dt	ice volume ridging rate (category n)	m/s
E		
eice(n)	energy of melting of ice per unit area (in category n)	J/m ²
emissivity	emissivity of snow and ice	0.95

Continued on next page

Table 5.1 – continued from previous page

eps13	a small number	10^{-13}	
eps16	a small number	10^{-16}	
esno(n)	energy of melting of snow per unit area (in category n)	J/m^2	
evap	evaporative water flux	$\text{kg/m}^2/\text{s}$	
F			
faero_atm	aerosol deposition rate	$\text{kg/m}^2/\text{s}$	
faero_ocn	aerosol flux to the ocean	$\text{kg/m}^2/\text{s}$	
fbot_xfer_type	• type of heat transfer coefficient under ice		
fcondtop(n)(_f)	conductive heat flux	W/m^2	
ferrmax	max allowed energy flux error (thermodynamics)	$1 \times 10^{-3} \text{ W/m}^2$	
ffracn	fraction of fsurf used to melt pond ice		
fhocn	net heat flux to ocean	W/m^2	
fhocn_ai	grid-box-mean net heat flux to ocean (fhocn)	W/m^2	
first_ice	flag for initial ice formation		
flat	latent heat flux	W/m^2	
floediam	effective floe diameter for lateral melt	300. m	
floeshape	floe shape constant for lateral melt	0.66	
flux_bio	all biogeochemistry fluxes passed to ocean		
flux_bio_ai	all biogeochemistry fluxes passed to ocean, grid cell mean		
flw	incoming longwave radiation	W/m^2	
flwout	outgoing longwave radiation	W/m^2	
formdrag	• calculate form drag		
fpond	fresh water flux to ponds	$\text{kg/m}^2/\text{s}$	
fr_resp	bgc respiration fraction	0.05	
frain	rainfall rate	$\text{kg/m}^2/\text{s}$	
frazil	frazil ice growth	m	
fresh	fresh water flux to ocean	$\text{kg/m}^2/\text{s}$	
fresh_ai	grid-box-mean fresh water flux (fresh)	$\text{kg/m}^2/\text{s}$	
frz_onset	day of year that freezing begins		
frzmlt	freezing/melting potential	W/m^2	
frzmlt_init	freezing/melting potential at beginning of time step	W/m^2	
frzmlt_max	maximum magnitude of freezing/melting potential	1000. W/m^2	
frzpond	• Stefan refreezing of melt ponds	‘hlid’	
fsalt	net salt flux to ocean	$\text{kg/m}^2/\text{s}$	
fsalt_ai	grid-box-mean salt flux to ocean (fsalt)	$\text{kg/m}^2/\text{s}$	
fsens	sensible heat flux	W/m^2	
fsnow	snowfall rate	$\text{kg/m}^2/\text{s}$	
fsnowrdg	snow fraction that survives in ridging	0.5	
fsurf(n)(_f)	net surface heat flux excluding fcondtop	W/m^2	
fsw	incoming shortwave radiation	W/m^2	
fswabs	total absorbed shortwave radiation	W/m^2	
fswfac	scaling factor to adjust ice quantities for updated data		
fswint	shortwave absorbed in ice interior	W/m^2	
fswpenl	shortwave penetrating through ice layers	W/m^2	

Continued on next page

Table 5.1 – continued from previous page

fswthru	shortwave penetrating to ocean	W/m^2	
fswthru_ai	grid-box-mean shortwave penetrating to ocean (fswthru)	W/m^2	
fyear	current data year		
fyear_final	last data year		
fyear_init	• initial data year		
G			
gravit	gravitational acceleration	9.80616 m/s^2	
grow_net	specific biogeochemistry growth rate per grid cell	s^{-1}	
Gstar	piecewise-linear ridging participation function parameter	0.15	
H			
heat_capacity	• if true, use salinity-dependent thermodynamics	T	
hfrazilmin	minimum thickness of new frazil ice	0.05 m	
hi_min	minimum ice thickness for thinnest ice category	0.01 m	
hi_ssl	ice surface scattering layer thickness	0.05 m	
hicen	ice thickness in category n	m	
highfreq	• high-frequency atmo coupling	F	
hin_old	ice thickness prior to growth/melt	m	
hin_max	category thickness limits	m	
hmix	ocean mixed layer depth	20. m	
hour	hour of the year		
hp0	pond depth at which shortwave transition to bare ice occurs	0.2 m	
hp1	• critical ice lid thickness for topo ponds (dEdd)	0.01 m	
hpmmin	minimum melt pond depth (shortwave)	0.005 m	
hpondn	melt pond depth	m	
hs_min	minimum thickness for which T_s is computed	$1. \times 10^{-4} \text{ m}$	
hs0	• snow depth at which transition to ice occurs (dEdd)	0.03 m	
hs1	• snow depth of transition to pond ice	0.03 m	
hs_ssl	snow surface scattering layer thickness	0.04 m	
Hstar	determines mean thickness of ridged ice	25. m	
I			
i0vis	fraction of penetrating visible solar radiation	0.70	
ice_ic	• choice of initial conditions		
ice_stdout	unit number for standard output		
ice_stderr	unit number for standard error output		
ice_ref_salinity	reference salinity for ice–ocean exchanges	4. ppt	
iceruf	ice surface roughness	$5. \times 10^{-4} \text{ m}$	
idate	the date at the end of the current time step (yyyymmdd)		
idate0	initial date		
igrid	interface points for vertical bio grid		
int_kind	definition of an integer	selected_real_kind(6)	
istep	local step counter for time loop		

Continued on next page

Table 5.1 – continued from previous page

istep0	• number of steps taken in previous run	0
istep1	total number of steps at current time step	
Iswabs	shortwave radiation absorbed in ice layers	W/m ²
J		
K		
kalg	• absorption coefficient for algae	
kappav	visible extinction coefficient in ice, wavelength < 700nm	1.4 m ⁻¹
kcatbound	• category boundary formula	
kg_to_g	kg to g conversion factor	1000.
kice	thermal conductivity of fresh ice ([6])	2.03 W/m/deg
kitd	• type of itd conversions (0 = delta function, 1 = linear remap)	1
krdg_partic	• ridging participation function	1
krdg_redist	• ridging redistribution function	1
krdgn	mean ridge thickness per thickness of ridging ice	
kseaice	thermal conductivity of ice for zero-layer thermodynamics	2.0 W/m/deg
ksno	thermal conductivity of snow	0.30 W/m/deg
kstrength	• ice strength formulation (1 = [43], 0 = [19])	1
ktherm	• thermodynamic formulation (0 = zero-layer, 1 = [6], 2 = mushy)	
L		
l_brine	flag for brine pocket effects	
l_conservation_check	if true, check conservation when ridging	
l_mpond_fresh	• if true, retain (topo) pond water until ponds drain	
Lfresh	latent heat of melting of fresh ice = Lsub - Lvap	J/kg
lhcoef	transfer coefficient for latent heat	
lmask_n(s)	northern (southern) hemisphere mask	
log_kind	definition of a logical variable	kind(.true.)
Lsub	latent heat of sublimation for fresh water	2.835 × 10 ⁶ J/kg
Lvap	latent heat of vaporization for fresh water	2.501 × 10 ⁶ J/kg
M		
m_to_cm	meters to cm conversion	100.
m1	constant for lateral melt rate	1.6 × 10 ⁻⁶ m/s deg ^{-m2}
m2	constant for lateral melt rate	1.36
m2_to_km2	m ² to km ² conversion	1 × 10 ⁻⁶
max_blocks	maximum number of blocks per processor	
max_ntrcr	maximum number of tracers available	5
maxraft	maximum thickness of ice that rafts	1. m
mday	day of the month	
meltb	basal ice melt	m
meltil	lateral ice melt	m
melts	snow melt	m

Continued on next page

Table 5.1 – continued from previous page

meltt	top ice melt	m
min_salin	threshold for brine pockets	0.1 ppt
mlt_onset	day of year that surface melt begins	
month	the month number	
monthp	previous month number	
mps_to_cmpdy	m per s to cm per day conversion	8.64×10^6
mu_rdg	• e-folding scale of ridged ice	
N		
n_aero	number of aerosol species	
natmiter	• number of atmo boundary layer iterations	5
nbtrcr	number of biology tracers	
ncat	number of ice categories	5
ndtd	• number of dynamics/advection steps under thermo	1
new_day	flag for beginning new day	
new_hour	flag for beginning new hour	
new_month	flag for beginning new month	
new_year	flag for beginning new year	
nhlat	northern latitude of artificial mask edge	30°S
nilyr	number of ice layers in each category	7
nit	nitrate concentration	mmol/m ³
nlt_bgc_[chem]	ocean sources and sinks for biogeochemistry	
nml_filename	namelist file name	
npt	• total number of time steps (dt)	
nslyr	number of snow layers in each category	
nspint	number of solar spectral intervals	
nt_<trcr>	tracer index	
ntrcr	number of tracers	
nu_diag	unit number for diagnostics output file	
nu_dump	unit number for dump file for restarting	
nu_forcing	unit number for forcing data file	
nu_nml	unit number for namelist input file	
nu_restart	unit number for restart input file	
nu_rst_pointer	unit number for pointer to latest restart file	
nx(y)_block	total number of gridpoints on block in x(y) direction	
nyr	year number	
O		
ocean_bio	concentrations of bgc constituents in the ocean	
oceanmixed_ice	• if true, use internal ocean mixed layer	
ocn_data_format	• format of ocean forcing files	
ocn_data_type	• source of ocean surface data	
omega	angular velocity of Earth	7.292×10^{-5} rad/s
opening	rate of ice opening due to divergence and shear	1/s
P		
p001	1/1000	
p01	1/100	
p025	1/40	
p027	1/36	
p05	1/20	
p055	1/18	

Continued on next page

Table 5.1 – continued from previous page

p1	1/10		
p111	1/9		
p15	15/100		
p166	1/6		
p2	1/5		
p222	2/9		
p25	1/4		
p333	1/3		
p4	2/5		
p5	1/2		
p52083	25/48		
p5625m	-9/16		
p6	3/5		
p666	2/3		
p75	3/4		
phi_c_slow_mode	• critical liquid fraction		
phi_i_mushy	• solid fraction at lower boundary		
phi_sk	skeletal layer porosity		
phi_snow	• snow porosity for brine height tracer		
pi	π		
pi2	2π		
pih	$\pi/2$		
piq	$\pi/4$		
pndaspect	• aspect ratio of pond changes (depth:area)	0.8	
potT	atmospheric potential temperature	K	
PP_net	total primary productivity per grid cell	mg C/m ² /s	
precip_units	• liquid precipitation data units		
print_points	• if true, print point data	F	
Pstar	ice strength parameter	2.75×10^4 N/m	
puny	a small positive number	1×10^{-11}	
Q			
Qa	specific humidity at 10 m	kg/kg	
qdp	deep ocean heat flux	W/m ²	
qqqice	for saturated specific humidity over ice	1.16378×10^7 kg/m ³	
qqqocn	for saturated specific humidity over ocean	6.275724×10^6 kg/m ³	
Qref	2m atmospheric reference specific humidity	kg/kg	
R			
R_C2N	algal carbon to nitrate factor	7. mole/mole	
R_gC2molC	mg/mmol carbon	12.01 mg/mole	
R_chl2N	algal chlorophyll to nitrate factor	3. mg/mmol	
R_ice	• parameter for Delta-Eddington ice albedo		
R_pnd	• parameter for Delta-Eddington pond albedo		
R_S2N	algal silicate to nitrate factor	0.03 mole/mole	
R_snw	• parameter for Delta-Eddington snow albedo		
r16_kind	definition of quad precision	selected_real_kind(26)	

Continued on next page

Table 5.1 – continued from previous page

Rac_rapid_mode	• critical Rayleigh number	10	
rdg_conv	convergence for ridging	1/s	
rdg_shear	shear for ridging	1/s	
real_kind	definition of single precision real	selected_real_kind(6)	
refindx	refractive index of sea ice	1.310	
restart	• if true, initialize using restart file instead of defaults	T	
restart_age	• if true, read age restart file		
restart_bgc	• if true, read bgc restart file		
restart_dir	• path to restart/dump files		
restart_file	• restart file prefix		
restart_[tracer]	• if true, read tracer restart file		
restore_bgc	• if true, restore nitrate/silicate to data		
restore_ice	• if true, restore ice state along lateral boundaries		
restore_ocn	• restore sst to data		
rfracmin	• minimum melt water fraction added to ponds	0.15	
rfracmax	• maximum melt water fraction added to ponds	1.0	
rhoa	air density	kg/m ³	
rhofresh	density of fresh water	1000.0 kg/m ³	
rhoi	density of ice	917. kg/m ³	
rhos	density of snow	330. kg/m ³	
rhosi	average sea ice density (for hbrine tracer)	940. kg/m ³	
rhow	density of seawater	1026. kg/m ³	
rnilyr	real(nlyr)		
rside	fraction of ice that melts laterally		
rsnw_fresh	freshly fallen snow grain radius	100. × 10 ⁻⁶ m	
rsnw_mlt	• melting snow grain radius	1000. × 10 ⁻⁶ m	
rsnw_nonmelt	nonmelting snow grain radius	500. × 10 ⁻⁶ m	
rsnw_sig	standard deviation of snow grain radius	250. × 10 ⁻⁶ m	
S			
salinz	ice salinity profile	ppt	
saltmax	max salinity, at ice base (<i>[6]</i>)	3.2 ppt	
scale_factor	scaling factor for shortwave radiation components		
sec	seconds elapsed into idate		

Continued on next page

Table 5.1 – continued from previous page

secday	number of seconds in a day	86400.	
shcoef	transfer coefficient for sensible heat		
shear	strain rate II component	1/s	
shlat	southern latitude of artificial mask edge	30°N	
shortwave	• flag for shortwave parameterization ('default' or 'dEdd')		
sil	silicate concentration	mmol/m ³	
sk_l	skeletal layer thickness	0.03 m	
snoice	snow-ice formation	m	
snowpatch	length scale for parameterizing nonuniform snow coverage	0.02 m	
skl_bgc	• biogeochemistry on/off		
spval	special value (single precision)	10 ³⁰	
spval_dbl	special value (double precision)	10 ³⁰	
ss_tltx(y)	sea surface in the x(y) direction	m/m	
sss	sea surface salinity	ppt	
sst	sea surface temperature	C	
Sswabs	shortwave radiation absorbed in snow layers	W/m ²	
stefan-boltzmann	Stefan-Boltzmann constant	$5.67 \times 10^{-8} \text{ W/m}^2 \text{ K}^4$	
stop_now	if 1, end program execution		
strairx(y)	stress on ice by air in the x(y)-direction (centered in U cell)	N/m ²	
strairx(y)T	stress on ice by air, x(y)-direction (centered in T cell)	N/m ²	
strax(y)	wind stress components from data	N/m ²	
strength	ice strength (pressure)	N/m	
stress12	internal ice stress, σ_{12}	N/m	
stressm	internal ice stress, $\sigma_{11} - \sigma_{22}$	N/m	
stressp	internal ice stress, $\sigma_{11} + \sigma_{22}$	N/m	
strintx(y)	divergence of internal ice stress, x(y)	N/m ²	
strocnx(y)	ice-ocean stress in the x(y)-direction (U-cell)	N/m ²	
strocnx(y)T	ice-ocean stress, x(y)-dir. (T-cell)	N/m ²	
strltlx(y)	surface stress due to sea surface slope	N/m ²	
swndf	incoming shortwave radiation, near IR, diffuse	W/m ²	
swndr	incoming shortwave radiation, near IR, direct	W/m ²	
swvdf	incoming shortwave radiation, visible, diffuse	W/m ²	
swvdr	incoming shortwave radiation, visible, direct	W/m ²	
T			
Tair	air temperature at 10 m	K	
tday	absolute day number		
Tf	freezing temperature	C	
Tffresh	freezing temp of fresh ice	273.15 K	
tfrz_option	• form of ocean freezing temperature		
thinS	minimum ice thickness for brine tracer		
time	total elapsed time	s	
time_forc	time of last forcing update	s	

Continued on next page

Table 5.1 – continued from previous page

Timelt	melting temperature of ice top surface	0. C
TLAT	latitude of cell center	radians
TLON	longitude of cell center	radians
tmask	land/boundary mask, thickness (T-cell)	
tmass	total mass of ice and snow	kg/m ²
Tmin	minimum allowed internal temperature	-100. C
Tmltz	melting temperature profile of ice	
Tocnfrz	temperature of constant freezing point parameterization	-1.8 C
tr_aero	• if true, use aerosol tracers	
tr_bgc_[tracer]	• if true, use biogeochemistry tracers	
tr_brine	• if true, use brine height tracer	
tr_FY	• if true, use first-year area tracer	
tr_iage	• if true, use ice age tracer	
tr_lvl	• if true, use level ice area and volume tracers	
tr_pond_cesm	• if true, use CESM melt pond scheme	
tr_pond_lvl	• if true, use level-ice melt pond scheme	
tr_pond_topo	• if true, use topo melt pond scheme	
trcr	ice tracers	
trcr_depend	tracer dependency on basic state variables	
Tref	2m atmospheric reference temperature	K
trestore	• restoring time scale	days
Tsf_errmax	max allowed T_{sf} error (thermodynamics)	$5. \times 10^{-4}$ deg
Tsfc(n)	temperature of ice/snow top surface (in category n)	C
Tsmelt	melting temperature of snow top surface	0. C
TTTice	for saturated specific humidity over ice	5897.8 K
TTToen	for saturated specific humidity over ocean	5107.4 K
U		
uatm	wind velocity in the x direction	m/s
umin	min wind speed for turbulent fluxes	1. m/s
uocn	ocean current in the x-direction	m/s
update_ocn_f	• if true, include frazil ice fluxes in ocean flux fields	
use_leap_years	• if true, include leap days	
ustar_min	• minimum friction velocity under ice	
uvel	x-component of ice velocity	m/s
V		
vatm	wind velocity in the y direction	m/s
vice(n)	volume per unit area of ice (in category n)	m
vicen_init	ice volume at beginning of timestep	m
viscosity_dyn	dynamic viscosity of brine	1.79×10^{-3} kg/m/s
vocn	ocean current in the y-direction	m/s
vonkar	von Karman constant	0.4
vraftn	volume of rafted ice	m

Continued on next page

Table 5.1 – continued from previous page

vrdsn	volume of ridged ice	m	
vsno(n)	volume per unit area of snow (in category n)	m	
vvel	y-component of ice velocity	m/s	
W			
warmice	value for constant albedo parameterization	0.68	
warmsno	value for constant albedo parameterization	0.77	
wind	wind speed	m/s	
write_restart	if 1, write restart now		
X			
Y			
ycycle	• number of years in forcing data cycle		
yday	day of the year		
year_init	• the initial year		
Z			
zlvl	atmospheric level height	m	
zref	reference height for stability	10. m	
zTrf	reference height for T_{ref} , Q_{ref} , U_{ref}	2. m	
zvir	gas constant (water vapor)/gas constant (air) - 1	0.606	

REFERENCES

References

- search

BIBLIOGRAPHY

- [1] T.L. Amundrud, H. Mallin, and R.G. Ingram. Geometrical constraints on the evolution of ridged sea ice. *J. Geophys. Res. Oceans*, 2004. URL: <http://dx.doi.org/10.1029/2003JC002251>.
- [2] K.C. Armour, C.M. Bitz, L. Thompson, and E.C. Hunke. Controls on Arctic sea ice from first-year and multi-year ice survivability. *J. Climate*, 24:2378–2390, 2011. URL: <http://dx.doi.org/10.1175/2010JCLI3823.1>.
- [3] S.P.S. Arya. A drag partition theory for determining the large-scale roughness parameter and wind stress on the Arctic pack ice. *J. Geophys. Res.*, 80:3447–3454, 1975. URL: <http://dx.doi.org/10.1029/JC080i024p03447>.
- [4] A. Assur. Composition of sea ice and its tensile strength. In *Arctic sea ice; conference held at Easton, Maryland, February 24–27, 1958*, volume 598, pages 106–138. Publs. Natl. Res. Coun. Wash., Washington, D.C., 1958.
- [5] C.M. Bitz, M.M. Holland, M. Eby, and A.J. Weaver. Simulating the ice-thickness distribution in a coupled climate model. *J. Geophys. Res. Oceans*, 106:2441–2463, 2001. URL: <http://dx.doi.org/10.1029/1999JC000113>.
- [6] C.M. Bitz and W.H. Lipscomb. An energy-conserving thermodynamic sea ice model for climate study. *J. Geophys. Res. Oceans*, 104(C7):15669–15677, 1999. URL: <http://dx.doi.org/10.1029/1999JC900100>.
- [7] B.P. Briegleb and B. Light. *A Delta-Eddington multiple scattering parameterization for solar radiation in the sea ice component of the Community Climate System Model*. NCAR Technical Note NCAR/TN-472+STR, National Center for Atmospheric Research, 2007. URL: https://github.com/CICE-Consortium/CICE/blob/master/doc/PDF/BL_NCAR2007.pdf.
- [8] P. Duarte and Coauthors. Sea ice thermohaline dynamics and biogeochemistry in the Arctic Ocean: Empirical and model results. *J. Geophys. Res. Biogeo.*, 122:1632–1654, 2017. URL: <https://doi.org/10.1002/2016JG003660>.
- [9] E.E. Ebert, J.L. Schramm, and J.A. Curry. Disposition of solar radiation in sea ice and the upper ocean. *J. Geophys. Res. Oceans*, 100:15965–15975, 1995. URL: <http://dx.doi.org/10.1029/95JC01672>.
- [10] H. Eicken, T.C. Grenfell, D.K. Perovich, J.A. Richter-Menge, and K. Frey. Hydraulic controls of summer Arctic pack ice albedo. *J. Geophys. Res. Oceans*, 2004. URL: <http://dx.doi.org/10.1029/2003JC001989>.
- [11] D.L. Feltham, N. Untersteiner, J.S. Wettlaufer, and M.G. Worster. Sea ice is a mushy layer. *Geophys. Res. Lett.*, 2006. URL: <http://dx.doi.org/10.1029/2006GL026290>.
- [12] G.M. Flato and W.D. Hibler. Ridging and strength in modeling the thickness distribution of Arctic sea ice. *J. Geophys. Res. Oceans*, 100:18611–18626, 1995. URL: <http://dx.doi.org/10.1029/95JC02091>.
- [13] D. Flocco and D.L. Feltham. A continuum model of melt pond evolution on Arctic sea ice. *J. Geophys. Res. Oceans*, 2007. URL: <http://dx.doi.org/10.1029/2006JC003836>.
- [14] D. Flocco, D.L. Feltham, and A.K. Turner. Incorporation of a physically based melt pond scheme into the sea ice component of a climate model. *J. Geophys. Res. Oceans*, 2010. URL: <http://dx.doi.org/10.1029/2009JC005568>.
- [15] D. Flocco, D. Schroeder, D.L. Feltham, and E.C. Hunke. Impact of melt ponds on Arctic sea ice simulations from 1990 to 2007. *J. Geophys. Res. Oceans*, 2012. URL: <http://dx.doi.org/10.1029/2012JC008195>.

- [16] National Centers for Environmental Information. World Ocean Atlas Version 2. *Natl. Ocn. and Atm. Admin.*, 2013. URL: <https://www.nodc.noaa.gov/OC5/woa13/>.
- [17] H.E. Garcia, R.A. Locarnini, T.P. Boyer, and J.I. Antonov. Nutrients (phosphate, nitrate, silicate). In *World Ocean Atlas 2005*, volume 4. NOAA Atlas NESDIS 64, NOAA, 2006.
- [18] K.M. Golden, H. Eicken, A.L. Heaton, J. Miner, D.J. Pringle, and J. Zhu. Thermal evolution of permeability and microstructure in sea ice. *Geophys. Res. Lett.*, 2007. URL: <http://dx.doi.org/10.1029/2007GL030447>.
- [19] W.D. Hibler. A dynamic thermodynamic sea ice model. *J. Phys. Oceanogr.*, 9:817–846, 1979. URL: [http://dx.doi.org/10.1175/1520-0485\(1979\)009<T1>textless{}0815:ADTSIM<T1>textgreater{}2.0.CO;2](http://dx.doi.org/10.1175/1520-0485(1979)009<T1>textless{}0815:ADTSIM<T1>textgreater{}2.0.CO;2).
- [20] W.D. Hibler. Modeling a variable thickness sea ice cover. *Mon. Wea. Rev.*, 108:1943–1973, 1980. URL: [http://dx.doi.org/10.1175/1520-0493\(1980\)108<T1>textless{}1943:MAVTSIT1<T1>textgreater{}2.0.CO;2](http://dx.doi.org/10.1175/1520-0493(1980)108<T1>textless{}1943:MAVTSIT1<T1>textgreater{}2.0.CO;2).
- [21] M.M. Holland, D.A. Bailey, B.P. Briegleb, B. Light, and E. Hunke. Improved sea ice shortwave radiation physics in CCSM4: The impact of melt ponds and aerosols on Arctic sea ice. *J. Climate*, 25:1413–1430, 2012. URL: <http://dx.doi.org/10.1175/JCLI-D-11-00078.1>.
- [22] E.C. Hunke and C.M. Bitz. Age characteristics in a multidecadal Arctic sea ice simulation. *J. Geophys. Res. Oceans*, 2009. URL: <http://dx.doi.org/10.1029/2008JC005186>.
- [23] E.C. Hunke, D.A. Hebert, and O. Lecomte. Level-ice melt ponds in the Los Alamos Sea Ice Model, CICE. *Ocean Modelling*, 71:26–42, 2013. URL: <http://dx.doi.org/10.1016/j.ocemod.2012.11.008>.
- [24] N. Jeffery and E.C. Hunke. Modeling the winter-spring transition of first-year ice in the western Weddell Sea. *J. Geophys. Res. Oceans*, 119:5891–5920, 2014. URL: <http://dx.doi.org/10.1002/2013JC009634>.
- [25] N. Jeffery, E.C. Hunke, and S.M. Elliott. Modeling the transport of passive tracers in sea ice. *J. Geophys. Res. Oceans*, 116:2156–2202, 2011. URL: <https://doi.org/10.1029/2010JC006527>.
- [26] M. Jin, C. Deal, J. Wang, K.H. Shin, N. Tanaka, T.E. Whiteledge, S.H. Lee, and R.R. Gradinger. Controls of the landfast ice-ocean ecosystem offshore Barrow, Alaska. *Ann. Glaciol.*, 44:63–72, 2006. URL: <https://github.com/CICE-Consortium/CICE/blob/master/doc/PDF/JDWSTWLG06.pdf>.
- [27] R.E. Jordan, E.L. Andreas, and A.P. Makshtas. Heat budget of snow-covered sea ice at North Pole 4. *J. Geophys. Res. Oceans*, 104(C4):7785–7806, 1999. URL: <http://dx.doi.org/10.1029/1999JC900011>.
- [28] B.G. Kauffman and W.G. Large. The CCSM coupler, version 5.0.1. *NCAR Tech. Note*, 2002. URL: https://github.com/CICE-Consortium/CICE/blob/master/doc/PDF/KL_NCAR2002.pdf.
- [29] R.W. Lindsay. Temporal variability of the energy balance of thick Arctic pack ice. *J. Climate*, 11:313–333, 1998. URL: [https://doi.org/10.1175/1520-0442\(1998\)011<T1>textless{}0313:TVOTEB<T1>textgreater{}2.0.CO;2](https://doi.org/10.1175/1520-0442(1998)011<T1>textless{}0313:TVOTEB<T1>textgreater{}2.0.CO;2).
- [30] W.H. Lipscomb. *Modeling the Thickness Distribution of Arctic Sea Ice*. Dept. of Atmospheric Sciences University of Washington, Seattle, 1998. PhD thesis. URL: <http://hdl.handle.net/1773/10081>.
- [31] W.H. Lipscomb. Remapping the thickness distribution in sea ice models. *J. Geophys. Res. Oceans*, 106:13989–14000, 2001. URL: <http://dx.doi.org/10.1029/2000JC000518>.
- [32] W.H. Lipscomb, E.C. Hunke, W. Maslowski, and J. Jakacki. Ridging, strength, and stability in high-resolution sea ice models. *J. Geophys. Res. Oceans*, 2007. URL: <http://dx.doi.org/10.1029/2005JC003355>.
- [33] P. Lu, Z. Li, B. Cheng, and M. Lepparanta. A parametrization fo the ice-ocean drag coefficient. *J. Geophys. Res. Oceans*, 2011. URL: <http://dx.doi.org/10.1029/2010JC006878>.
- [34] C. Lüpkes, V.M. Gryanik, J. Hartmann, and E.L. Andreas. A parametrization, based on sea ice morphology, of the neutral atmospheric drag coefficients for weather prediction and climate models. *J. Geophys. Res. Atmos.*, 2012. URL: <http://dx.doi.org/10.1029/2012JD017630>.
- [35] G.A. Maykut. Large-scale heat exchange and ice production in the central Arctic. *J. Geophys. Res. Oceans*, 87:7971–7984, 1982. URL: <http://dx.doi.org/10.1029/JC087iC10p07971>.

- [36] G.A. Maykut and M.G. McPhee. Solar heating of the Arctic mixed layer. *J. Geophys. Res. Oceans*, 100:24691–24703, 1995. URL: <http://dx.doi.org/10.1029/95JC02554>.
- [37] G.A. Maykut and D.K. Perovich. The role of shortwave radiation in the summer decay of a sea ice cover. *J. Geophys. Res. Oceans*, 92:7032–7044, 1987. URL: <http://dx.doi.org/10.1029/JC092iC07p07032>.
- [38] G.A. Maykut and N. Untersteiner. Some results from a time dependent thermodynamic model of sea ice. *J. Geophys. Res.*, 76:1550–1575, 1971. URL: <http://dx.doi.org/10.1029/JC076i006p01550>.
- [39] D. Notz. *Thermodynamic and Fluid-Dynamical Processes in Sea Ice*. University of Cambridge, UK, 2005. PhD thesis. URL: <http://ulmss-newton.lib.cam.ac.uk/vwebv/holdingsInfo?bibId=27224>.
- [40] N. Ono. Specific heat and heat of fusion of sea ice. In H. Oura, editor, *Physics of Snow and Ice*, volume I, pages 599–610. Institute of Low Temperature Science, Hokkaido, Japan, 1967.
- [41] D.J. Pringle, H. Eicken, H.J. Trodahl, and L.G.E. Backstrom. Thermal conductivity of landfast Antarctic and Arctic sea ice. *J. Geophys. Res. Oceans*, 2007. URL: <http://dx.doi.org/10.1029/2006JC003641>.
- [42] A.F. Roberts, A. Craig, W. Maslowski, R. Osinski, A. Duvivier, M. Hughes, B. Nijssen, J.J. Cassano., and M. Brunke. Simulating transient ice-ocean ekman transport in the regional arctic system model and community earth system model. *Ann. Glaciol.*, 56(69):211–228, 2015. URL: <https://doi.org/10.3189/2015AoG69A760>.
- [43] D.A. Rothrock. The energetics of plastic deformation of pack ice by ridging. *J. Geophys. Res.*, 80:4514–4519, 1975. URL: <http://dx.doi.org/10.1029/JC080i033p04514>.
- [44] S. Saha, S. Moorthi, X. Wu, J. Wang, and Coauthors. Two modes of sea-ice gravity drainage: a parameterization for large-scale modeling. *J. Climate*, 27:2185–2208, 2014. URL: <http://dx.doi.org/10.1175/JCLI-D-12-00823.1>.
- [45] W. Schwarzacher. Pack ice studies in the Arctic Ocean. *J. Geophys. Res.*, 64:2357–2367, 1959. URL: <http://dx.doi.org/10.1029/JZ064i012p02357>.
- [46] A.J. Semtner. A Model for the Thermodynamic Growth of Sea Ice in Numerical Investigations of Climate. *J. Phys. Oceanogr.*, 6:379–389, 1976. URL: [http://dx.doi.org/10.1175/1520-0485\(1976\)006<T1>textless{}0379:AMFTTGVT1textgreater{}2.0.CO;2](http://dx.doi.org/10.1175/1520-0485(1976)006<T1>textless{}0379:AMFTTGVT1textgreater{}2.0.CO;2).
- [47] G. Siedler and H. Peters. Physical properties (general) of sea water. In *Landolt-Börnstein: Numerical data and functional relationships in science and technology, New Series V/3a*, pages 233–264. Springer, 1986.
- [48] M. Steele. Sea ice melting and floe geometry in a simple ice-ocean model. *J. Geophys. Res. Oceans*, 97:17729–17738, 1992. URL: <http://dx.doi.org/10.1029/92JC01755>.
- [49] P.D. Taylor and D.L. Feltham. A model of melt pond evolution on sea ice. *J. Geophys. Res. Oceans*, 2004. URL: <http://dx.doi.org/10.1029/2004JC002361>.
- [50] A.S. Thorndike, D.A. Rothrock, G.A. Maykut, and R. Colony. The thickness distribution of sea ice. *J. Geophys. Res.*, 80:4501–4513, 1975. URL: <http://dx.doi.org/10.1029/JC080i033p04501>.
- [51] H.J. Trodahl, S.O.F. Wilkinson, M.J. McGuinness, and T.G. Haskeel. Thermal conductivity of sea ice: dependence on temperature and depth. *Geophys. Res. Lett.*, 28:1279–1282, 2001. URL: <http://dx.doi.org/10.1029/2000GL012088>.
- [52] M. Tsamados, D.L. Feltham, D. Schroeder, D. Flocco, S.L. Farrell, N.T. Kurtz, S.W. Laxon, and S. Bacon. Impact of variable atmospheric and oceanic form drag on simulations of Arctic sea ice. *J. Phys. Oceanogr.*, 44:1329–1353, 2014. URL: <https://doi.org/10.1175/JPO-D-13-0215.1>.
- [53] A.K. Turner, E.C. Hunke, and C.M. Bitz. Two modes of sea-ice gravity drainage: a parameterization for large-scale modeling. *J. Geophys. Res. Oceans*, 118:2279–2294, 2013. URL: <http://dx.doi.org/10.1002/jgrc.20171>.
- [54] N. Untersteiner. Calculations of temperature regime and heat budget of sea ice in the Central Arctic. *J. Geophys. Res.*, 69:4755–4766, 1964. URL: <http://dx.doi.org/10.1029/JZ069i022p04755>.